

The image is a large, symmetrical, abstract graphic composed of the letters 'S' and 'Y' arranged in a grid-like pattern. The overall shape is a stylized 'W' or a complex letter 'M'. The top part is a wide horizontal bar made of 'S's, with 'Y's forming a central vertical column. The sides are formed by 'S's and 'Y's, creating a sense of depth and structure. The bottom part is a wide horizontal bar made of 'S's, with 'Y's forming a central vertical column. The entire graphic is composed of black letters on a white background.

EX
VO4[illegible]

EXCEPTION
Table of contents

- EXCEPTION HANDLING

L 6

16-SEP-1984 00:06:28 VAX/VMS Macro V04-00

Page 0

(2)	129	ACCESS VIOLATION FAULT
(3)	204	ARITHMETIC TRAPS
(4)	240	AST DELIVERY STACK FAULT
(5)	273	BREAKPOINT FAULT
(6)	292	CHANGE MODE TO SUPERVISOR TRAP
(7)	319	CHANGE MODE TO USER TRAP
(8)	353	COMPATIBILITY MODE FAULTS
(9)	406	KERNEL STACK NOT VALID FAULT
(10)	426	SIGNAL UNRECOVERABLE MACHINE CHECK
(11)	449	OPCODE RESERVED TO CUSTOMER FAULT
(12)	468	OPCODE RESERVED TO DIGITAL FAULT
(13)	501	PAGE READ FAULT
(14)	533	RESERVED ADDRESSING MODE FAULT
(15)	553	RESERVED OPERAND FAULT
(16)	572	TBIT PENDING TRAP
(17)	599	SYSTEM SERVICE FAILURE EXCEPTION
(18)	631	REFLECT EXCEPTION FROM MODE OTHER THAN KERNEL
(19)	708	COMMON EXCEPTION EXIT
(20)	857	SEARCH FOR AND CALL CONDITION HANDLER
(21)	1033	SEARCH FOR CONDITION HANDLER
(22)	1143	EXE\$SIGTORET - TURN EXCEPTION INTO RETURN STATUS
(23)	1177	EXE\$EXPANDSTK - EXPAND USER STACK
(24)	1227	EXE\$MCHK_PRTCT - MACHINE CHECK RECOVERY BLOCK


```
0000 1 .TITLE EXCEPTION - EXCEPTION HANDLING
0000 2 .IDENT 'V04-000'
0000 3
0000 4
0000 5 *****
0000 6 *****
0000 7 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY *
0000 8 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS. *
0000 9 * ALL RIGHTS RESERVED. *
0000 10 *
0000 11 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED *
0000 12 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE *
0000 13 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER *
0000 14 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY *
0000 15 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY *
0000 16 * TRANSFERRED. *
0000 17 *
0000 18 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE *
0000 19 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT *
0000 20 * CORPORATION. *
0000 21 *
0000 22 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS *
0000 23 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL. *
0000 24 *
0000 25 *
0000 26 *****
0000 27 *****
0000 28 D. N. CUTLER 6-JUL-76
0000 29
0000 30 MODIFIED BY:
0000 31
0000 32 V03-007 WMC0002 Wayne Cardoza 28-Aug-1984
0000 33 Mask spurious accvio caused by 780/785 hardware bug.
0000 34
0000 35 V03-006 LY00B2 Larry Yetto 10-FEB-1984 09:56
0000 36 Fix truncation error
0000 37
0000 38 V03-005 LJK0260 Lawrence J. Kenah 5-Feb-1984
0000 39 Allow exception dispatching to take a detour through an
0000 40 instruction emulator so that the exception parameters can
0000 41 be modified to describe an exception at the site of the
0000 42 emulated instruction rather than inside the emulator.
0000 43 Correct errors that appeared in comments.
0000 44
0000 45 V03-004 ACG0393 Andrew C. Goldstein, 20-Jan-1984 1:38
0000 46 Fix FP validation in condition handler search; also
0000 47 call EXESUNWIND directly to avoid P1 vectors
0000 48
0000 49 V03-003 WMC0001 Wayne Cardoza 28-Oct-1983
0000 50 Change mode to user or supervisor handlers should not get
0000 51 control in privileged modes.
0000 52
0000 53 V03-002 ACG0348 Andrew C. Goldstein, 4-Aug-1983 17:01
0000 54 Fix unwinding to frame of exception
0000 55
0000 56 V03-001 ACG0310 Andrew C. Goldstein, 31-Jan-1983 13:44
0000 57 Fix probing of stack after expansion
```



```
0000 58 :  
0000 59 :  
0000 60 : HARDWARE EXCEPTION HANDLING  
0000 61 :  
0000 62 : *****  
0000 63 :  
0000 64 : FAIR WARNING!! THE EXCEPTION REFLECTION AND CONDITION HANDLING CODE IN  
0000 65 : THIS MODULE CRAWLS WITH ASSUMPTIONS ABOUT THE FORMAT OF THE STACK AND  
0000 66 : ARGUMENT LISTS, AS DOCUMENTED IN VARIOUS COMMENTS THROUGHOUT. SINCE  
0000 67 : THE STACK POINTER MOVES FREQUENTLY, NO ATTEMPT HAS BEEN MADE TO USE  
0000 68 : SYMBOLIC OFFSETS FOR STACK RELATIVE REFERENCES. CHANGES TO THE STACK  
0000 69 : FORMAT SHOULD BE MADE ONLY AFTER THOROUGH INSPECTION AND UNDERSTANDING  
0000 70 : OF THE CODE (NOT TO MENTION APPENDIX C OF THE ARCHITECTURE HANDBOOK).  
0000 71 : NOTE ALSO THAT LIB$SIGNAL MUST TRACK THE STACK FORMATS USED HERE.  
0000 72 :  
0000 73 : *****  
0000 74 :  
0000 75 : MACRO LIBRARY CALLS  
0000 76 :  
0000 77 :  
0000 78 : SCHFDEF ;DEFINE CONDITION HANDLING ARGLIST OFFSETS  
0000 79 : $IPLDEF ;DEFINE INTERRUPT PRIORITY LEVELS  
0000 80 : $MCHKDEF ;DEFINE MACHINE CHECK RECOVERY BITS  
0000 81 : $PCBDEF ;DEFINE PCB OFFSETS  
0000 82 : $PHDDEF ;DEFINE PHD OFFSETS  
0000 83 : $PRDEF ;DEFINE PROCESSOR REGISTERS  
0000 84 : $PSLDEF ;DEFINE PROCESSOR STATUS FIELDS  
0000 85 : $SSDEF ;DEFINE SYSTEM STATUS VALUES  
0000 86 : $STSDEF ;DEFINE STATUS CODE FIELDS  
0000 87 : $VADEF ;DEFINE VIRTUAL ADDRESS FIELDS  
0000 88 :  
0000 89 :  
0000 90 : LOCAL SYMBOLS  
0000 91 :  
0000 92 : CALL FRAME OFFSET DEFINITIONS  
0000 93 :  
0000 94 :  
00000000 0000 95 HANDLER=0 ;CONDITION HANDLER ADDRESS  
00000004 0000 96 SAVPSW=4 ;SAVED PSW FROM CALL  
00000006 0000 97 SAVMSK=6 ;REGISTER SAVE MASK  
00000008 0000 98 SAVAP=8 ;SAVED AP REGISTER IMAGE  
0000000C 0000 99 SAVFP=12 ;SAVED FP REGISTER IMAGE  
00000010 0000 100 SAVPC=16 ;SAVED PC REGISTER IMAGE  
00000014 0000 101 SAVRG=20 ;OTHER SAVED REGISTER IMAGES  
0000 102 :  
0000 103 :  
0000 104 : LOCAL DATA  
0000 105 :  
0000 106 :  
00000000 0000 107 .PSECT YEXEPAGED1, LONG  
0000 108 :  
00000000 0000 109 FINAL_IDX = 0 ;INDICES TO FETCH MESSAGE ADDRESSES  
00000001 0000 110 ATTCONSTO_IDX = 1  
00000002 0000 111 BADHANDLER_IDX = 2  
00000003 0000 112 BADAST_IDX = 3  
0000 113 :  
0000 114 MSG_VECTOR:
```


00000010:	0000	115	.ADDRESS	FINALMSG
00000033:	0004	116	.ADDRESS	ATTCONSTO_MSG
00000052:	0008	117	.ADDRESS	BADHANDLER_MSG
00000083:	000C	118	.ADDRESS	BADAST_MSG
	0010	119		
72 6F 20 6B 63 61 74 73 20 64 61 62	0010	120	FINALMSG:	;FINAL EXCEPTION MESSAGE
20 72 65 6C 64 6E 61 68 20 6F 6E 20	001C	121	.ASCIIZ	/bad stack or no handler specified./ ;
00 2E 64 65 69 66 69 63 65 70 73	0028			
	0033	122	ATTCONSTO_MSG:	;ATTEMPT TO CONTINUE FROM STOP MESSAGE
63 20 6F 74 20 74 70 6D 65 74 74 61	0033	123	.ASCIIZ	/attempt to continue from STOP./
6D 6F 72 66 20 65 75 6E 69 74 6E 6F	003F			
00 2E 50 4F 54 53 20	004B			
	0052	124	BADHANDLER_MSG:	;BAD CONDITION HANDLER MESSAGE ADDRESS
64 6E 6F 63 20 64 69 6C 61 76 6E 69	0052	125	.ASCIIZ	/invalid condition handler address or entry mask./
65 6C 64 6E 61 68 20 6E 6F 69 74 69	005E			
72 6F 20 73 73 65 72 64 64 61 20 72	006A			
2E 6B 73 61 6D 20 79 72 74 6E 65 20	0076			
	0082			
	0083	126	BADAST_MSG:	;BAD AST MESSAGE ADDRESS
20 54 53 41 20 64 69 6C 61 76 6E 69	0083	127	.ASCIIZ	/invalid AST address or entry mask./
65 20 72 6F 20 73 73 65 72 64 64 61	008F			
00 2E 6B 73 61 6D 20 79 72 74 6E	009B			


```
00A6 129 .SBTTL ACCESS VIOLATION FAULT
00A6 130 :+
00A6 131 : EXE$ACVIOLAT - ACCESS VIOLATE FAULT
00A6 132 :
00A6 133 : THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN AN ACCESS VIOLATION IS
00A6 134 : DETECTED. THE STATE OF THE STACK ON ENTRY IS:
00A6 135 :
00A6 136 : 00(SP) = ACCESS VIOLATION REASON MASK.
00A6 137 : 04(SP) = ACCESS VIOLATION VIRTUAL ADDRESS.
00A6 138 : 08(SP) = EXCEPTION PC.
00A6 139 : 12(SP) = EXCEPTION PSL.
00A6 140 :
00A6 141 : ACCESS VIOLATION REASON MASK FORMAT IS:
00A6 142 :
00A6 143 : BIT 0 = TYPE OF ACCESS VIOLATION.
00A6 144 : 0 = PTE ACCESS CODE DID NOT PERMIT INTENDED ACCESS.
00A6 145 : 1 = POLR, P1LR, OR SOLR LENGTH VIOLATION.
00A6 146 : BIT 1 = PTE REFERENCE.
00A6 147 : 0 = SPECIFIED VIRTUAL ADDRESS NOT ACCESSIBLE.
00A6 148 : 1 = ASSOCIATED PAGE TABLE ENTRY NOT ACCESSIBLE.
00A6 149 : BIT 2 = INTENDED ACCESS TYPE.
00A6 150 : 0 = READ.
00A6 151 : 1 = MODIFY.
00A6 152 :
00A6 153 : THE EXCEPTION NAME FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE
00A6 154 : PUSHED ON THE STACK. FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
00A6 155 : -
00A6 156 :
00000000 157 .PSECT $AEXENONPAGED, LONG
0000 158 .ALIGN LONG
0000 159 EXE$ACVIOLAT:: : ACCESS VIOLATION FAULTS
03 0C AE 02 18 ED 0000 160 CMPZV #PSL$V_CURMOD, #PSL$S_CURMOD, 12(SP), #PSL$C_USER : CHECK FOR USER
17 12 0006 161 BNEQ 20$ : NO, REALLY AN ACCESS VIOLATION
OF BB 0008 162 PUSHR #^M<R0,R1,R2,R3> : SAVE WORKING REGISTERS
52 14 AE D0 000A 163 MOVL <4+<4*4>>(SP), R2 : GET BASE ADDRESS FOR EXTEND
0000041A'EF 16 000E 164 JSB EXE$EXPANDSTK : EXPAND STACK
06 50 E9 0014 165 BLBC R0, 10$ : BR IF CANT EXTEND
OF BA 0017 166 POPR #^M<R0,R1,R2,R3> : RESTORE REGISTERS
5E 08 C0 0019 167 5$: ADDL #8, SP : CLEAN EXCEPTION PARAMETERS FROM STACK
02 001C 168 REI : AND RETURN TO RETRY INSTRUCTION
OF BA 001D 169 10$: POPR #^M<R0,R1,R2,R3> : RESTORE REGISTERS
001F 170 20$:
001F 171 :+
001F 172 : THE FOLLOWING SECTION OF CODE IS USED TO MASK A SPURIOUS ACCESS VIOLATION
001F 173 : WHICH IS SEEN ON THE 780/785. AT THIS TIME THE EXACT CAUSE IS UNKNOWN. IT IS
001F 174 : ASSUMED TO BE EITHER HARDWARE OR MICROCODE.
001F 175 :
001F 176 : THE SPURIOUS ACCVIO ONLY OCCURS WHEN AN INSTRUCTION STARTS ON THE LAST BYTE
001F 177 : OF A PAGE. THE EXACT CIRCUMSTANCES ARE UNKNOWN SINCE IT CANNOT BE RELIABLY
001F 178 : REPRODUCED.
001F 179 : -
04 AE 01FF 8F B3 001F 180 BITW #^X1FF, 4(SP) : WAS FIRST BYTE OF PAGE REFERENCED
3C 12 0025 181 BNEQ ACVIOLAT : NO
6E D5 0027 182 TSTL (SP) : WAS IT READ ACCESS
38 12 0029 183 BNEQ ACVIOLAT : NO
7E 04 AE 08 AE C3 002B 184 SUBL3 8(SP), 4(SP), -(SP) : GET DIFFERENCE BETWEEN PC, REFERENCE
01 8E D1 0031 185 CMPL (SP)+, #1 : ARE THEY ADJACENT
```



```
2D 12 0034 186 BNEQ ACVIOLAT ; NO
    01 0036 187 NOP ; LEAVE ROOM FOR AN INVALID IF WE NEED IT
    01 0037 188 NOP
    01 0038 189 NOP
    01 0039 190 NOP
    01 003A 191 NOP
    01 003B 192 NOP
04 BE 01 00 0C 003C 193 PROBER #0,#1,@4(SP) ; IS IT SPURIOUS
00000000'EF 00000000'EF 13 0041 194 BEQL ACVIOLAT ; NO
00000000'EF 00000000'EF 13 0043 195 CMPL EXESGL_ABSTIM,EXESGL_BADACV_T ; ARE THEY COMING FAST
00000000'EF 00000000'EF 13 004E 196 BEQL ACVIOLAT ; YES
00000000'EF 00000000'EF D0 0050 197 MOVL EXESGL_ABSTIM,EXESGL_BADACV_T ; SAVE TIME OF THIS ONE
00000000'EF 00000000'EF D6 005B 198 INCL EXESGL_BADACV_C ; COUNT THEM
    B6 11 0061 199 BRB $$ ; GO RETRY
    0063 200 ACVIOLAT:
7E 0C 3C 0063 201 MOVZWL #$$$ ACCVIO,-(SP) ; SET EXCEPTION NAME
00EE 31 0066 202 BRW EX$ARG ;
```



```
0069 204 .SBTTL ARITHMETIC TRAPS
0069 205 :+
0069 206 : EXES$ARITH - ARITHMETIC TRAPS
0069 207 :
0069 208 : THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN AN ARITHMETIC TRAP IS
0069 209 : DETECTED AT THE END OF AN INSTRUCTION. THE STATE OF THE STACK ON ENTRY
0069 210 : IS:
0069 211 :
0069 212 : 00(SP) = ARITHMETIC EXCEPTION CODE.
0069 213 : 04(SP) = EXCEPTION PC.
0069 214 : 08(SP) = EXCEPTION PSL.
0069 215 :
0069 216 : POSSIBLE ARITHMETIC EXCEPTION CODES ARE:
0069 217 :
0069 218 : 0 = UNDEFINED.
0069 219 : 1 = INTERGER OVERFLOW.
0069 220 : 2 = INTEGER DIVIDE BY ZERO.
0069 221 : 3 = FLOATING OVERFLOW.
0069 222 : 4 = FLOATING OR DECIMAL DIVIDE BY ZERO.
0069 223 : 5 = FLOATING UNDERFLOW.
0069 224 : 6 = DECIMAL STRING OVERFLOW.
0069 225 : 7 = SUBSCRIPT RANGE TRAP IN INDEX INSTRUCTION.
0069 226 : 8 = FLOATING OVERFLOW FAULT.
0069 227 : 9 = FLOATING DIVIDE BY ZERO FAULT.
0069 228 : 10 = FLOATING UNDERFLOW FAULT.
0069 229 :
0069 230 : THE EXCEPTION NAME FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE
0069 231 : PUSHED ON THE STACK. FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
0069 232 : -
0069 233 :
0069 234 : .ALIGN LONG
006C 235 EXES$ARITH::
6E 6E 08 C4 006C 236 MULL #8,(SP) ;ARITHMETIC TRAPS
0474 8F A0 006F 237 ADDW #SS$ ARTRES,(SP) ;CALCULATE EXCEPTION NAME OFFSET
0104 31 0074 238 BRW EX3ARG ;CALCULATE ACTUAL EXCEPTION NAME
;
;
```

```
0077 240 .SBTTL AST DELIVERY STACK FAULT
0077 241 :+
0077 242 : EXE$ASTFLT - AST DELIVERY STACK FAULT
0077 243 :
0077 244 : THIS ROUTINE IS ENTERED VIA A JMP FROM THE AST DELIVERY MODULE
0077 245 : WHEN AN INVALID STACK IS DETECTED WHILE ATTEMPTING TO DELIVER AN
0077 246 : AST. THE STATE OF THE STACK ON ENTRY IS:
0077 247 :
0077 248 : 00(SP) = SP VALUE AT FAULT (UNMODIFIED BY AST DELIVERY).
0077 249 : 04(SP) = AST PARAMETER OF FAILED AST.
0077 250 : 08(SP) = PC AT AST DELIVERY INTERRUPT.
0077 251 : 12(SP) = PSL AT AST DELIVERY INTERRUPT.
0077 252 : 16(SP) = PC TO WHICH AST WOULD HAVE BEEN DELIVERED.
0077 253 : 20(SP) = PSL AT WHICH AST WOULD HAVE BEEN DELIVERED.
0077 254 :
0077 255 : THE EXCEPTION NAME FOLLOWED BY THE NUMBER OF ARGUMENTS ARE PUSHED
0077 256 : ON THE STACK. FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
0077 257 :
0077 258 : NOTE THAT THE PREVIOUS MODE FIELD IN THE PSL IS KERNEL MODE IN THIS
0077 259 : ENTRY POINT, SINCE AST'S (AND AST FAULTS) RESULT FROM INTERRUPTS, AS
0077 260 : OPPOSED TO ALL OTHER EXCEPTIONS WHICH RESULT FROM FAULTS OR TRAPS.
0077 261 : SINCE THE EXCEPTION MAIN BODY EXPECTS PREVIOUS MODE TO BE THE MODE
0077 262 : IN WHICH THE EXCEPTION OCCURRED, AND THE MODE TO WHICH IT WILL BE
0077 263 : REPORTED, WE MUST FIX IT UP ACCORDINGLY.
0077 264 :-
0077 265 :
0077 266 EXE$ASTFLT::
0077 267 MOVZWL #SS$_ASTFLT,-(SP) ;AST DELIVERY STACK FAULT
0077 268 PUSHL #7 ;PUSH EXCEPTION CODE
0077 269 BICL3 #^C<PSL$M PRVMOD>,28(SP),-(SP) ;AND COUNT OF ARGUMENTS
0077 270 PUSHAB W^EXE$EXCEPTION ;CONSTRUCT PROPER PSL
0077 271 REI ;AND EXCEPTION ENTRY POINT
;SET PSL AND ENTER COMMON EXCEPTION CODE
```

7E 040C 8F 3C 0077 267
07 DD 007C 268
7E 1C AE FF3FFFFFFF 8F CB 007E 269
018F'CF 9F 0087 270
02 008B 271


```
008C 273 .SBTTL BREAKPOINT FAULT
008C 274 :+
008C 275 : EXES$BREAK - BREAKPOINT FAULT
008C 276 :
008C 277 : THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN A BREAKPOINT
008C 278 : INSTRUCTION IS EXECUTED. THE STATE OF THE STACK ON ENTRY IS:
008C 279 :
008C 280 : 00(SP) = EXCEPTION PC.
008C 281 : 04(SP) = EXCEPTION PSL.
008C 282 :
008C 283 : THE EXCEPTION NAME FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE
008C 284 : PUSHED ON THE STACK. FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
008C 285 :-
008C 286 :
008C 287 .ALIGN LONG
008C 288 EXES$BREAK::
008C 289 MOVZWL #SS$ BREAK,-(SP)
0091 290 BRW EX3ARG
;BREAKPOINT FAULT
;SET EXCEPTION NAME
;
```

7E 0414 8F 3C
00E7 31 0091

```
0094 292 .SBTTL CHANGE MODE TO SUPERVISOR TRAP
0094 293 :+
0094 294 : EX$CMODSUPR - CHANGE MODE TO SUPERVISOR TRAP
0094 295 :
0094 296 : THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN A CHANGE MODE TO SUPER-
0094 297 : VISOR INSTRUCTION IS EXECUTED. THE STATE OF THE STACK ON ENTRY IS:
0094 298 :
0094 299 : 00(SP) = CHANGE MODE CODE.
0094 300 : 04(SP) = EXCEPTION PC.
0094 301 : 08(SP) = EXCEPTION PSL.
0094 302 :
0094 303 : IF THE PROCESS HAS DECLARED A CHANGE MODE TO SUPERVISOR HANDLER, THEN THE
0094 304 : EXCEPTION IS DIRECTLY VECTORED TO THE SPECIFIED HANDLER. ELSE THE EXCEPTION
0094 305 : NAME FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE PUSHED ON THE STACK.
0094 306 : FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
0094 307 :-
0094 308
0094 309 .ALIGN LONG
0094 310 EX$CMODSUPR::
0094 311 MOVZWL #SS$CMODSUPR,-(SP) ;CHANGE MODE TO SUPERVISOR TRAP
0099 312 CMPZV #PSL$V_CURMOD,#PSL$S_CURMOD- ;SET EXCEPTION NAME
009C 313 12(SP),#PSL$C_SUPER ;WERE WE IN USER OR SUPER MODE
009F 314 BLSS 20$ ;NO - DON'T GIVE CONTROL TO HANDLER
00A1 315 PUSHL @#CTL$GL_CMSUPR ;GET CONTENTS OF CHANGE MODE VECTOR
00A7 316 BRB EXCCMD ;
00A9 317 20$: BRW EX$SXT ;
```

7E 041C 8F 3C 0094 311
02 02 18 ED 0099 312
02 0C AE 009C 313
08 19 009F 314
00000000'9F DD 00A1 315
16 11 00A7 316
00DB 31 00A9 317


```
00AC 319 .SBTTL CHANGE MODE TO USER TRAP
00AC 320 :+
00AC 321 : EXE$CMODUSER - CHANGE MODE TO USER TRAP
00AC 322 :
00AC 323 : THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN A CHANGE MODE TO USER
00AC 324 : INSTRUCTION IS EXECUTED. THE STATE OF THE STACK ON ENTRY IS:
00AC 325 :
00AC 326 : 00(SP) = CHANGE MODE CODE.
00AC 327 : 04(SP) = EXCEPTION PC.
00AC 328 : 08(SP) = EXCEPTION PSL.
00AC 329 :
00AC 330 : IF THE PROCESS HAS DECLARED A CHANGE MODE TO USER HANLDER, THEN THE EXCEPTION
00AC 331 : IS VECTORED DIRECTLY TO THE SPECIFIED HANDLER. ELSE THE EXCEPTION NAME FOLLOWED
00AC 332 : BY THE NUMBER OF ARGUMENTS ARE PUSHED ON THE STACK. FINAL PROCESSING IS ACCOM-
00AC 333 : PLISHED IN COMMON CODE.
00AC 334 : IF THIS CODE IS ENTERED IN OTHER THAN USER MODE, IT IS TREATED AS THOUGH NO
00AC 335 : USER HANDLER WERE DELARED.
00AC 336 :-
00AC 337 :
00AC 338 .ALIGN LONG
00AC 339 .ENABL LSB
00AC 340 EXE$CMODUSER:: ;CHANGE MODE TO USER TRAP
7E 0424 8F 3C 00AC 341 MOVZWL #SS$ CMODUSER,-(SP) ;SET EXCEPTION NAME
03 02 18 ED 00B1 342 CMPZV #PSL$V_CURMOD,#PSL$S_CURMOD,-
03 0C AE 00B4 343 12(SP),#PSL$C_USER ;WERE WE IN USER MODE
00000000'9F DD 00B7 344 BNEQ 20$ ;NO - DON'T GIVE CONTROL TO HANDLER
04 13 00B9 345 PUSHL @#CTL$GL_CMUSER ;GET CONTENTS OF CHANGE MODE VECTOR
6E 8ED0 00BF 346 EXCCMD: BEQL 10$ ;IF EQL NO DISPATCHER SPECIFIED
05 00C1 347 POPL (SP) ;REMOVE EXCEPTION NAME FROM STACK
5E 04 C0 00C4 348 RSB ;
00BC 31 00C5 349 10$: ADDL #4,SP ;CLEAN STACK
00CB 350 20$: BRW EX$SXT ;
00CB 351 .DSABL LSB ;
```



```
00CB 353 .SBTTL COMPATIBILITY MODE FAULTS
00CB 354 :+
00CB 355 : EX$COMPAT - COMPATIBILITY MODE FAULT
00CB 356 :
00CB 357 : THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN A COMPATIBILITY MODE
00CB 358 : EXCEPTION IS DETECTED. THE STATE OF THE STACK ON ENTRY IS:
00CB 359 :
00CB 360 : 00(SP) = COMPATIBILITY EXCEPTION CODE.
00CB 361 : 04(SP) = EXCEPTION PC.
00CB 362 : 08(SP) = EXCEPTION PSL.
00CB 363 :
00CB 364 : POSSIBLE COMPATIBILITY EXCEPTION CODES ARE:
00CB 365 :
00CB 366 : 0 = RESERVED INSTRUCTION EXECUTION.
00CB 367 : 1 = BPT INSTRUCTION EXECUTION.
00CB 368 : 2 = IOT INSTRUCTION EXECUTION.
00CB 369 : 3 = EMT INSTRUCTION EXECUTION.
00CB 370 : 4 = TRAP INSTRUCTION EXECUTION.
00CB 371 : 5 = ILLEGAL INSTRUCTION EXECUTION.
00CB 372 : 6 = ODD ADDRESS FAULT.
00CB 373 : 7 = TBIT TRAP.
00CB 374 :
00CB 375 : THE EXCEPTION NAME FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE
00CB 376 : PUSHED ON THE STACK. FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
00CB 377 : -
00CB 378 :
00CB 379 .ALIGN LONG
00CC 380 EX$COMPAT::
00CC 381 MOVQ R0,@#CTLSAL_CMCNTX ;COMPATIBILITY MODE FAULTS
00D3 382 MOVAL @#CTLSAL_CMCNTX+8,R0 ;SAVE R0,R1 IN COMPATIBILITY CONTEXT REGION
00DA 383 MOVQ R2,(R0)+ ;GET ADDRESS OF COMPATIBILITY CONTEXT AREA
00DD 384 MOVQ R4,(R0)+ ;SAVE R2,R3
00E0 385 MOVL R6,(R0)+ ;SAVE R4,R5
00E3 386 MOVL (SP)+,(R0)+ ;SAVE R6
00E6 387 MOVQ (SP)+,(R0) ;SAVE EXCEPTION CODE AND REMOVE FROM STACK
00E9 388 PUSHL #<PSL$C_USER@PSL$V_PRVMOD>!<PSL$C_USER@PSL$V_CURMOD> ;SAVE PC AND PSL AND REMOVE FROM STACK
00EF 389 PUSHL @#CTLSGE_CMHANDLR ;FABRICATE PSL
00F5 390 BEQL 20$ ;COMPATIBILITY MODE HANDLER ADDRESS
00F7 391 REI ;BRANCH IF NONE SPECIFIED
00F8 392 :
00F8 393 :
00F8 394 : NO COMPATIBILITY MODE HANDLER WAS DECLARED. RESTORE THE STACK AND
00F8 395 : SAVED REGISTER, AND CONTINUE THROUGH NORMAL EXCEPTION CODE. R0 NOW
00F8 396 : POINTS TO THE SAVED PC IN THE COMPATIBILITY CONTEXT AREA.
00F8 397 :
00F8 398 :
00F8 399 20$: MOVQ (R0),(SP) ;RESTORE EXCEPTION PC AND PSL
00FB 400 PUSHL -(R0) ;PUSH EXCEPTION CODE AGAIN
00FD 401 MOVL -28(R0),R0 ;RESTORE R0 FROM TOP OF CONTEXT AREA
0101 402 MOVZWL #SS$_COMPAT,-(SP) ;SET EXCEPTION NAME
0106 403 EX4ARG: PUSHL #4 ;SET NUMBER OF SIGNAL ARGUMENTS
0108 404 BRW EX$EXCEPTION ;FINISH IN COMMON CODE
```

00000000'9F 50 7D 00CC 380
50 00000008'9F DE 00D3 381
80 52 7D 00DA 382
80 54 7D 00DD 383
80 56 DO 00E0 384
80 8E DO 00E3 385
60 8E 7D 00E6 386
03C00000 8F DD 00E9 387
00000000'9F DD 00EF 388
01 13 00F5 389
02 00F7 390
00F8 391
00F8 392
00F8 393
00F8 394
00F8 395
00F8 396
00F8 397
00F8 398
6E 60 7D 00F8 399
70 DD 00FB 400
50 E4 A0 DO 00FD 401
7E 042C 8F 3C 0101 402
04 DD 0106 403
0084 31 0108 404


```
010B 406 .SBTTL KERNEL STACK NOT VALID FAULT
010B 407 :+
010B 408 : EXESKERSTKNV - KERNEL STACK NOT VALID FAULT
010B 409 :
010B 410 : THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN A KERNEL STACK NOT
010B 411 : VALID IS DETECTED DURING A CHANGE MODE INSTRUCTION, DURING AN REI
010B 412 : INSTRUCTION, OR DURING AN ATTEMPT TO PUSH EXCEPTION INFORMATION ON
010B 413 : THE KERNEL STACK. THIS EXCEPTION RUNS ON THE INTERRUPT STACK. THE
010B 414 : STATE OF THE STACK ON ENTRY IS:
010B 415 :
010B 416 : 00(SP) = EXCEPTION PC.
010B 417 : 04(SP) = EXCEPTION PSL.
010B 418 :
010B 419 : A FATAL KERNEL STACK NOT VALID BUGCHECK IS DECLARED.
010B 420 :-
010B 421 :
010B 422 .ALIGN LONG
010C 423 EXESKERSTKNV:: ;KERNEL STACK NOT VALID FAULT
010C 424 BUG_CHECK KRNLSTAKNV,FATAL ;KERNEL STACK NOT VALID
```

```
0110 426 .SBTTL SIGNAL UNRECOVERABLE MACHINE CHECK
0110 427 :+
0110 428 : EXE$MCHECK - SIGNAL UNRECOVERABLE MACHINE CHECK
0110 429 :
0110 430 : THIS ROUTINE IS ENTERED FROM THE MACHINE CHECK HANDLER TO SIGNAL
0110 431 : THE ERROR BACK TO EITHER USER OR SUPERVISOR MODE. IF THE MACHINE
0110 432 : CHECK OCCURRED IN EXEC OR KERNEL MODE CONTROL DOES NOT COME HERE
0110 433 : AND INSTEAD THE MACHINE CHECK HANDLER BUGCHECKS.
0110 434 : STATE OF THE STACK ON ENTRY IS:
0110 435 :
0110 436 : 00(SP) = EXCEPTION PC
0110 437 : 04(SP) = EXCEPTION PSL
0110 438 :
0110 439 : POSSIBLE CODES ARE:
0110 440 :
0110 441 :
0110 442 : NO ALIGNMENT IS NECESSARY HERE, REI GETS US HERE
0110 443 :-
0110 444
0110 445 EXE$MCHECK::
7E 02BC 8F 3C 0110 446 MOVZWL #SS$ MCHECK, -(SP) ;SET EXCEPTION NAME
64 11 0115 447 BRB EX3ARG ;FINISH IN COMMON CODE
```


EXCEPTION
V04-000

- EXCEPTION HANDLING
OPCODE RESERVED TO CUSTOMER FAULT

M 7

16-SEP-1984 00:06:28 VAX/VMS Macro V04-00
5-SEP-1984 03:41:43 [SYS.SRC]EXCEPTION.MAR;1

Page 14
(11)

```
0117 449 .SBTTL OPCODE RESERVED TO CUSTOMER FAULT
0117 450 :+
0117 451 : EX$OPCCUS - OPCODE RESERVED TO CUSTOMER FAULT
0117 452 :
0117 453 : THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN AN OPCODE THAT IS RESERVED
0117 454 : TO CUSTOMERS IS EXECUTED. THE STATE OF THE STACK ON ENTRY IS:
0117 455 :
0117 456 : 00(SP) = EXCEPTION PC.
0117 457 : 04(SP) = EXCEPTION PSL.
0117 458 :
0117 459 : THE EXCEPTION NAME FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE
0117 460 : PUSHED ON THE STACK. FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
0117 461 :-
0117 462 :
0117 463 .ALIGN LONG
0118 464 EX$OPCCUS::
0118 465 MOVZWL #SS$ OPCCUS, -(SP)
011D 466 BRB EX3ARG
; OPCODE RESERVED TO CUSTOMERS FAULT
; SET EXCEPTION NAME
;
```

7E 0434 8F 3C
5C 11 011D

```
011F 468 .SBTTL OPCODE RESERVED TO DIGITAL FAULT
011F 469 :+
011F 470 : EX$OPCDEC - OPCODE RESERVED TO DIGITAL FAULT
011F 471 :
011F 472 : THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN AN OPCODE THAT IS RESERVED
011F 473 : TO DIGITAL IS EXECUTED. THE STATE OF THE STACK ON ENTRY IS:
011F 474 :
011F 475 : 00(SP) = EXECPTION PC.
011F 476 : 04(SP) = EXCEPTION PSL.
011F 477 :
011F 478 : THE EXCEPTION NAME FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE
011F 479 : PUSHED ON THE STACK. FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
011F 480 :-
011F 481
011F 482 .ALIGN LONG
0120 483 EX$OPCDEC::
00 BE FF 8F 91 0120 484 CMPB #^XFF,a(SP) ;OPCODE RESERVED TO DIGITAL FAULT
07 13 0125 485 BEQL 20$ ;POSSIBLY A BUG CHECK?
7E 043C 8F 3C 0127 486 10$: MOVZWL #SS$,OPCDEC,-(SP) ;IF EQL YES
4D 11 012C 487 BRB EX3ARG ;SET EXCEPTION NAME
6E DD 012E 488 20$: PUSHL (SP) ;
6E D6 0130 489 INCL (SP) ;COPY ADDRESS OF INSTRUCTION
0132 490 IFNORD #1,a(SP),40$ ;CALCULATE ADDRESS OF NEXT BYTE
00 BE FE 8F 91 0139 491 CMPB #^XFE,a(SP) ;CAN NEXT BYTE BE READ?
08 13 013E 492 BEQL 30$ ;BUGCHECK WORD?
9E FD 8F 91 0140 493 CMPB #^XFD,a(SP)+ ;IF EQL YES
E1 12 0144 494 BNEQ 10$ ;BUGCHECK LONG?
7E D5 0146 495 TSTL -(SP) ;IF NEQ NO
8E D5 0148 496 30$: TSTL (SP)+ ;ADJUST STACK POINTER
FEB3' 31 014A 497 BRW EX$BUG_CHECK ;REMOVE INSTRUCTION ADDRESS FROM STACK
00 DD 014D 498 40$: PUSHL #0 ;
FEAE 31 014F 499 BRW EX$ACVIOLAT ;SET REASON FOR ACCESS VIOLATION
;
```



```
0152 501 .SBTTL PAGE READ FAULT
0152 502 :+
0152 503 : EXE$PAGRDERR - PAGE READ FAULT
0152 504 :
0152 505 : THIS ROUTINE IS ENTERED VIA A JUMP FROM THE TRANSLATION NOT VALID
0152 506 : EXCEPTION ROUTINE WHEN A READ ERROR OCCURS IN TRYING TO MAKE THE
0152 507 : DESIRED PAGE VALID. THE STATE OF THE STACK ON ENTRY IS:
0152 508 :
0152 509 : 00(SP) = TRANSLATION NOT VALID REASON MASK.
0152 510 : 04(SP) = TRANSLATION NOT VALID VIRTUAL ADDRESS.
0152 511 : 08(SP) = EXCEPTION PC.
0152 512 : 12(SP) = EXCEPTION PSL.
0152 513 :
0152 514 : TRANSLATION NOT VALID REASON MASK FORMAT IS:
0152 515 :
0152 516 : BIT 0 = 0 (USED ONLY FOR ACCESS VIOLATION).
0152 517 : BIT 1 = PTE REFERENCE.
0152 518 : 0 = SPECIFIED VIRTUAL ADDRESS NOT VALID.
0152 519 : 1 = ASSOCIATED PAGE TABLE ENTRY NOT VALID.
0152 520 : BIT 2 = INTENDED ACCESS TYPE.
0152 521 : 0 = READ.
0152 522 : 1 = MODIFY.
0152 523 :
0152 524 : THE EXCEPTION NAME FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE
0152 525 : PUSHED ON THE STACK. FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
0152 526 : -
0152 527 :
0152 528 EXE$PAGRDERR::
7E 0444 8F 3C 0152 529 MOVZWL #SS$_PAGRDERR,-(SP) ;PAGE READ ERROR
05 DD 0157 530 EX$ARG: PUSHL #5 ;SET EXCEPTION NAME
0033 31 0159 531 BRW EXE$EXCEPTION ;SET NUMBER OF SIGNAL ARGUMENTS
;FINISH IN COMMON CODE
```



```
015C 533 .SBTTL RESERVED ADDRESSING MODE FAULT
015C 534 ;+
015C 535 ; EXE$RADRMOD - RESERVED ADDRESSING MODE FAULT
015C 536 ;
015C 537 ; THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN AN ATTEMPT TO USE A
015C 538 ; RESERVED ADDRESSING MODE IS DETECTED. THE STATE OF THE STACK ON ENTRY
015C 539 ; IS:
015C 540 ;
015C 541 ; 00(SP) = EXCEPTION PC.
015C 542 ; 04(SP) = EXCEPTION PSL.
015C 543 ;
015C 544 ; THE EXCEPTION NAME FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE
015C 545 ; PUSHED ON THE STACK. FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
015C 546 ; -
015C 547 ;
015C 548 .ALIGN LONG
015C 549 EXE$RADRMOD::
7E 044C 8F 3C 015C 550 MOVZWL #SS$ RADRMOD, -(SP) ;RESERVED ADDRESSING MODE FAULT
18 11 0161 551 BRB EX3ARG ;SET EXCEPTION NAME
;
;
```



```
0163 553 .SBTTL RESERVED OPERAND FAULT
0163 554 ;+
0163 555 ; EXE$ROPRAND - RESERVED OPERAND FAULT
0163 556 ;
0163 557 ; THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN AN ATTEMPT TO USE A
0163 558 ; RESERVED OPERAND IS DETECTED. THE STATE OF THE STACK ON ENTRY IS:
0163 559 ;
0163 560 ; 00(SP) = EXCEPTION PC.
0163 561 ; 04(SP) = EXCEPTION PSL.
0163 562 ;
0163 563 ; THE EXCEPTION NAME FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE
0163 564 ; PUSHED ON THE STACK. FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
0163 565 ; -
0163 566 ;
0163 567 .ALIGN LONG
0164 568 EXE$ROPRAND:: ;RESERVED OPERAND FAULT
0164 569 MOVZWL #SS$ROPRAND,-(SP) ;SET EXCEPTION NAME
0169 570 BRB EX3ARG ;
```

7E 0454 8F 3C
10 11


```
016B 572 .SBTTL TBIT PENDING TRAP
016B 573 :+
016B 574 : EXESTBIT - TBIT PENDING TRAP
016B 575 :
016B 576 : THIS ROUTINE IS AUTOMATICALLY VECTORED TO WHEN A TBIT PENDING EXCEPTION
016B 577 : IS DETECTED AT THE END OF AN INSTRUCTION. THE STATE OF THE STACK ON ENTRY
016B 578 : IS:
016B 579 :
016B 580 : 00(SP) = EXCEPTION PC.
016B 581 : 04(SP) = EXCEPTION PSL.
016B 582 :
016B 583 : IF THE TRAP OCCURED FROM COMPATIBILITY MODE, THEN THE CODE FOR COMPATIBILITY
016B 584 : MODE TBIT TRAP (7) IS PUSHED ON THE STACK AND AN EXIT IS MADE THROUGH
016B 585 : THE COMPATIBILITY MODE EXCEPTION ROUTINE. ELSE THE TBIT EXCEPTION NAME
016B 586 : FOLLOWED BY THE NUMBER OF EXCEPTION ARGUMENTS ARE PUSHED ON THE STACK.
016B 587 : FINAL PROCESSING IS ACCOMPLISHED IN COMMON CODE.
016B 588 :-
016B 589
016B 590 .ALIGN LONG
016C 591 EXESTBIT::
016C 592 PUSHL #7
016E 593 BBC #PSL$V CM,8(SP),10$
0173 594 BRW EX$COMPAT
0176 595 10$: ADDW #SS$_TBIT-7,(SP)
017B 596 EX3ARG: PUSHL #3
017D 597 BRW EX$EXCEPTION

03 08 AE 07 DD 016C 591 EXESTBIT::
01 1F E1 016C 592 PUSHL #7
FF56 31 016E 593 BBC #PSL$V CM,8(SP),10$
6E 045D 8F A0 0173 594 BRW EX$COMPAT
03 DD 0176 595 10$: ADDW #SS$_TBIT-7,(SP)
000F 31 017B 596 EX3ARG: PUSHL #3
017D 597 BRW EX$EXCEPTION

: TBIT PENDING TRAP
: ASSUME TRAP FROM COMPATIBILITY MODE
: IF CLEAR, NOT FROM COMPATIBILITY MODE
: IF SET, GO TO COMPATIBILITY MODE CODE
: ADJUST NAME TO THAT FOR TBIT
: SET NUMBER OF SIGNAL ARGUMENTS
:
```



```
0180 599 .SBTTL SYSTEM SERVICE FAILURE EXCEPTION
0180 600 :+
0180 601 : EX$SSFAIL - SYSTEM SERVICE FAILURE EXCEPTION
0180 602 :
0180 603 : THIS ROUTINE IS JUMPED TO FROM THE SYSTEM SERVICE CHANGE MODE DISPATCHER
0180 604 : WHEN THE RETURN STATUS FROM A SYSTEM SERVICE INDICATES FAILURE, THE
0180 605 : PREVIOUS MODE WAS USER, AND THE CURRENT PROCESS IS ENABLED FOR SYSTEM
0180 606 : SERVICE FAILURE EXCEPTIONS. THE STATE OF THE STACK ON ENTRY IS:
0180 607 :
0180 608 : 00(SP) = CHANGE MODE PC.
0180 609 : 04(SP) = CHANGE MODE PSL.
0180 610 :
0180 611 : WITH:
0180 612 :
0180 613 : R0 = FINAL SYSTEM SERVICE STATUS.
0180 614 :-
0180 615
0180 616 EX$SSFAIL:: ;SYSTEM SERVICE FAILURE EXCEPTION
0180 617 PUSH R0 ;PUSH REASON FOR SERVICE FAILURE
7E 045C 50 DD 0182 618 MOVZWL #SS$_SSFAIL,-(SP) ;SET EXCEPTION NAME
0187 619
0187 620 :
0187 621 : THE FOLLOWING EXCEPTIONS CONVERGE TO THIS POINT:
0187 622 :
0187 623 : CHANGE MODE TO SUPERVISOR,
0187 624 : CHANGE MODE TO USER, AND
0187 625 : SYSTEM SERVICE FAILURE.
0187 626 :
0187 627 :
0187 628 EXSSXT: PUSHL #4 ;SET NUMBER OF SIGNAL ARGUMENTS
000000A6'EF DD 0189 629 JMP EX$REFLECT ;REFLECT EXCEPTION TO PREVIOUS MODE
```



```
018F 631 .SBTTL REFLECT EXCEPTION FROM MODE OTHER THAN KERNEL
018F 632 :+
018F 633 : EXE$REFLECT - REFLECT EXCEPTION FROM MODE OTHER THAN KERNEL
018F 634 :
018F 635 : THIS ROUTINE IS JUMPED TO REFLECT AN EXCEPTION FROM A MODE OTHER THAN KERNEL.
018F 636 : THE SIGNAL ARGUMENTS ARE ASSUMED TO BE SET UP PROPERLY ON THE STACK.
018F 637 : NOTE THAT THE PREVIOUS MODE FIELD OF THE PSL CONTAINS THE ACCESS MODE
018F 638 : OF THE EXCEPTION.
018F 639 :-
018F 640
000000A6 641 .PSECT YEXEPAGED1
00A6 642 EXE$REFLECT::
01 DD 00A6 643 PUSHL #1 ;REFLECT EXCEPTION
03 BB 00A8 644 PUSHR #M<R0,R1> ;SAVE CODE INDICATING SIGNAL
7E 03 CE 00AA 645 MNEGL #3,-(SP) ;SAVE REGISTERS R0 AND R1
5D DD 00AD 646 PUSHL FP ;SET INITIAL FRAME DEPTH
04 DD 00AF 647 PUSHL #4 ;SET INITIAL HANDLER ESTABLISHER FRAME
;SET NUMBER OF MECHANISM ARGUMENTS
00B1 648
00B1 649
00B1 650 : AT THIS POINT THE STACK HAS THE FOLLOWING FORMAT:
00B1 651 :
00B1 652 : 00(SP) = NUMBER OF MECHANISM ARGUMENTS (ALWAYS 4).
00B1 653 : 04(SP) = FP OF HANDLER ESTABLISHER FRAME (TENTATIVE).
00B1 654 : 08(SP) = FRAME DEPTH (ALWAYS -3).
00B1 655 : 12(SP) = SAVED R0.
00B1 656 : 16(SP) = SAVED R1.
00B1 657 : 20(SP) = FLAGS LONGWORD
00B1 658 : 24(SP) = NUMBER OF SIGNAL ARGUMENTS.
00B1 659 : 28(SP) = EXCEPTION NAME (INTEGER VALUE).
00B1 660 : 32(SP) = FIRST EXCEPTION PARAMETER (IF ANY).
00B1 661 : 36(SP) = SECOND EXCEPTION PARAMETER (IF ANY).
00B1 662 :
00B1 663 :
00B1 664 :
00B1 665 : 28+N*4(SP) = N'TH EXCEPTION PARAMETER (IF ANY).
00B1 666 : 28+N*4+4(SP) = EXCEPTION PC.
00B1 667 : 28+N*4+8(SP) = EXCEPTION PSL.
00B1 668 :
00B1 669 :
51 50 02 50 DC 00B1 670 MOVPSL R0 ;READ CURRENT PSL
18 EF 00B3 671 EXTZV #PSL$V_CURMOD,#PSL$S_CURMOD,R0,R1 ;CURRENT MODE KERNEL?
69 13 00B8 672 BEQL 30$ ;IF EQL YES
51 50 02 16 ED 00BA 673 CMPZV #PSL$V_PRVMOD,#PSL$S_PRVMOD,R0,R1 ;IS CURRENT EQL PREVIOUS?
68 13 00BF 674 BEQL 40$ ;IF EQL YES
00C1 675
00C1 676 :
00C1 677 : ADJUST PREVIOUS MODE STACK POINTER USING SYSTEM SERVICE
00C1 678 :
00C1 679 :
13 24 AE 1C BB 00C1 680 PUSHR #M<R2,R3,R4> ;SAVE REGISTERS R2, R3, AND R4
07 C1 00C3 681 ADDL3 #7,36(SP),R3 ;CALCULATE NUMBER OF LONGWORDS TO MOVE
01EF CF 9F 00C8 682 PUSHAB W^NORMAL ;ASSUME INFORMATION CAN BE COPIED
7E D4 00CC 683 CLRL -(SP) ;SET TO USE CURRENT STACK POINTER VALUE
6E 9F 00CE 684 PUSHAB (SP) ;PUSH ADDRESS TO STORE UPDATED STACK VALUE
7E 53 02 78 00D0 685 ASHL #2,R3,-(SP) ;CALCULATE STACK ADJUSTMENT VALUE
6E CE 00D4 686 MNEGL (SP),(SP) ;SET NEGATIVE ADJUSTMENT VALUE
7E 50 02 16 EF 00D7 687 EXTZV #PSL$V_PRVMOD,#PSL$S_PRVMOD,R0,-(SP) ;PUSH ACCESS MODE OF STACK
```


		03	DD	00DC	688	PUSHL	#3	;PUSH NUMBER OF ARGUMENTS
	00000000'9F	6E	FA	00DE	689	CALLG	(SP),@#SYSS\$ADJSTK	;ADJUST PREVIOUS MODE STACK POINTER
		33 50	E8	00E5	690	BLBS	R0,20\$;IF LBS SUCCESSFUL COMPLETION
	14 AE	0292'CF	9E	00E8	691 10\$:	MOVAB	W^BADSTACK,20(SP)	;SET BAD STACK RETURN
		52 04 AE	D0	00EE	692	MOVL	4(SP),R2	;RETRIEVE PREVIOUS ACCESS MODE
10 AE	00000000'9F42	42	D0	00F2	693	MOVL	@#CTL\$AL_STACK[R2],16(SP)	;SET TO USE SPECIFIED STACK POINTER VALUE
	00000000'EF	6E	FA	00FB	694	CALLG	(SP),SYSS\$ADJSTK	;RELOAD PREVIOUS MODE STACK POINTER
		16 50	E8	0102	695	BLBS	R0,20\$;IF LBS SUCCESSFUL COMPLETION
7E	00000000'9F42	04	C3	0105	696	SUBL3	#4,@#CTL\$AL_STACK[R2],-(SP)	;CALCULATE TOP ADDRESS OF STACK RANGE
	7E 6E	0C AE	C1	010E	697	ADDL3	12(SP),(SP),-(SP)	;CALCULATE BOTTOM ADDRESS OF STACK RANGE
		008C	30	0113	698	BSBW	CRESTACK	;RE-CREATE VIRTUAL SPACE UNDER STACK
		5E 08	C0	0116	699	ADDL	#8,SP	;REMOVE VIRTUAL ADDRESS DESCRIPTOR
		CD	11	0119	700	BRB	10\$;AND TRY AGAIN
				011B	701			
		5E 10	C0	011B	702 20\$:	ADDL	#16,SP	;REMOVE ARGUMENT LIST FROM STACK
		02	BA	011E	703	POPR	#^M<R1>	;GET NEW PREVIOUS MODE STACK POINTER VALUE
		01EB	31	0120	704	BRW	COPYARGS	
	0000019A'EF	17	0123	705 30\$:	JMP	REFLECT		
	00C3	31	0129	706 40\$:	BRW	NORMAL		


```
012C 708 .SBTTL COMMON EXCEPTION EXIT
012C 709 :
012C 710 : ALL EXCEPTIONS CONVERGE TO THIS POINT WITH:
012C 711 :
012C 712 : 00(SP) = NUMBER OF SIGNAL ARGUMENTS.
012C 713 : 04(SP) = EXCEPTION NAME (INTEGER VALUE).
012C 714 : 08(SP) = FIRST EXCEPTION PARAMETER (IF ANY).
012C 715 : 12(SP) = SECOND EXCEPTION PARAMETER (IF ANY).
012C 716 :
012C 717 :
012C 718 :
012C 719 : 04+N*4(SP) = N'TH EXCEPTION PARAMETER (IF ANY).
012C 720 : 04+N*4+4(SP) = EXCEPTION PC.
012C 721 : 04+N*4+8(SP) = EXCEPTION PSL.
012C 722 :
012C 723 : NOTE THAT THE PREVIOUS MODE FIELD OF THE PSL CONTAINS THE ACCESS MODE
012C 724 : OF THE EXCEPTION.
012C 725 :
012C 726 :
0000018F 727 .PSECT $AEXENONPAGED, LONG
018F 728 .ENABL LSB
018F 729 EXE$EXCEPTION:: :THIS LABEL MUST BE GLOBAL FOR MP CODE
01 DD 018F 730 PUSHL #1 ;SET CODE INDICATING SIGNAL
03 BB 0191 731 PUSHR #M<R0,R1> ;SAVE REGISTERS R0 AND R1
03 CE 0193 732 MNEGL #3,-(SP) ;SET INITIAL FRAME DEPTH
5D DD 0196 733 PUSHL FP ;SET INITIAL HANDLER ESTABLISHER FRAME
04 DD 0198 734 PUSHL #4 ;SET NUMBER OF MECHANISM ARGUMENTS
019A 735 :
019A 736 :
019A 737 : AT THIS POINT THE STACK HAS THE FOLLOWING FORMAT:
019A 738 :
019A 739 : 00(SP) = NUMBER OF MECHANISM ARGUMENTS (ALWAYS 4).
019A 740 : 04(SP) = FP OF HANDLER ESTABLISHER FRAME (TENTATIVE).
019A 741 : 08(SP) = FRAME DEPTH (ALWAYS -3).
019A 742 : 12(SP) = SAVED R0.
019A 743 : 16(SP) = SAVED R1.
019A 744 : 20(SP) = FLAGS LONGWORD
019A 745 : 24(SP) = NUMBER OF SIGNAL ARGUMENTS.
019A 746 : 28(SP) = EXCEPTION NAME (INTEGER VALUE).
019A 747 : 32(SP) = FIRST EXCEPTION PARAMETER (IF ANY).
019A 748 : 36(SP) = SECOND EXCEPTION PARAMETER (IF ANY).
019A 749 :
019A 750 :
019A 751 :
019A 752 : 28+N*4(SP) = N'TH EXCEPTION PARAMETER (IF ANY).
019A 753 : 28+N*4+4(SP) = EXCEPTION PC.
019A 754 : 28+N*4+8(SP) = EXCEPTION PSL.
019A 755 :
019A 756 :
019A 757 REFLECT: ;REFLECT EXCEPTION TO PROPER ACCESS MODE
50 18 AE 06 C1 019A 758 ADDL3 #6,24(SP),R0 ;CALCULATE LONGWORD OFFSET TO SAVED PSL
019F 759 ASSUME PSL$V CM EQ 31
6E40 D5 019F 760 TSTL (SP)[R0] ;PREVIOUSLY IN COMPATIBILITY MODE?
20 18 01A2 761 BGEQ 10$ ;BRANCH IF NOT
51 00000000'9F DE 01A4 762 MOVAL @#CTL$AL CMCNTX,R1 ;GET ADDRESS OF COMPATIBILITY CONTEXT AREA
81 0C AE 7D 01AB 763 MOVQ 12(SP),(R1)+ ;SAVE R0 AND R1
81 52 7D 01AF 764 MOVQ R2,(R1)+ ;SAVE R2 AND R3
```


81	54	7D	01B2	765	MOVQ	R4,(R1)+	:SAVE R4 AND R5
81	56	D0	01B5	766	MOVL	R6,(R1)+	:SAVE R6
81	08	9A	01B8	767	MOVZBL	#8,(R1)+	:SET CM EXCEPTION TYPE
81	FC	D0	01BB	768	MOVL	-4(SP)[R0],(R1)+	:SAVE PC
61	6E	D0	01C0	769	MOVL	(SP)[R0],(R1)	:SAVE PSL
	51	DC	01C4	770	MOVPSL	R1	:READ CURRENT PSL
	12	DB	01C6	771	MFPR	#PR\$,IPL,R0	:READ CURRENT IPL
50	02	D1	01C9	772	CMPL	#IPL\$,ASTDEL,R0	:INVALID PRIORITY LEVEL?
50	04	19	01CC	773	BLSS	20\$:IF LSS YES
04	51	1A	E1	774	BBC	#PSL\$V IS,R1,30\$:IF CLR, THEN NOT ON INTERRUPT STACK
			01D2	775	BUG CHECK	INVECEPTN,FATAL	:INVALID EXCEPTION
			01D6	776	IFNORD	#4,#CTL\$AL_STACK,20\$:IS THERE A CONTROL REGION?
			01E0	777			: (NOT SWAPPER,NULLPROC)
50	51	02	16	778	EXTZV	#PSL\$V_PVRMOD,#PSL\$S_PVRMOD,R1,R0	:EXTRACT PREVIOUS MODE FIELD
	06	12	01E5	779	BNEQ	35\$:IF EQL PREVIOUS MODE WAS KERNEL
	000001EF	17	01E7	780	JMP	NORMAL	
	0000012C	17	01ED	781	JMP	37\$:GOTO PAGED CODE
		0000	012C	782	.PSECT	YEXEPAGED1	
	1C	BB	012C	783	PUSHR	#*M<R2,R3,R4>	:SAVE REGISTERS R2, R3, R4
	01EF	9F	012E	784	PUSHAB	W*NORMAL	:ASSUME INFORMATION CAN BE COPIED
53	28	AE	07	785	MOVL	R0,R2	:SAVE PREVIOUS MODE
	51	52	DB	786	ADDL3	#7,40(SP),R3	:CALCULATE NUMBER OF LONGWORDS TO MOVE
		01E8	30	787	MFPR	R2,R1	:READ PREVIOUS MODE STACK POINTER
		14	12	788	BSBW	CHECK_STACK	:CHECK STACK RANGE
	52	03	D1	789	BNEQ	40\$:CONTINUE IF STACK OK
		28	12	790	CMPL	#PSL\$C_USER,R2	:IS IT USER MODE STACK FAULT?
		0E	BB	791	BNEQ	50\$:NO, THEN BAD STACK
	52	50	D0	792	PUSHR	#*M<R1,R2,R3>	:SAVE REGISTERS
		02CB	30	793	MOVL	R0,R2	:GET LOWEST STACK ADDRESS FROM CHECK_STACK
		0E	BA	794	BSBW	EX\$EXPANDSTK	:AND CALL TO EXPAND STACK
	1B	50	E9	795	POPR	#*M<R1,R2,R3>	:RESTORE REGISTERS
		E7	11	796	BLBC	R0,50\$:BR IF ANY ERROR TO DECLARE BAD STACK
			0154	797	BRB	38\$:CHECK THE STACK AGAIN
			0156	798			:NOTE- CHECK_STACK PREVENTS US FROM LOOPING
00000000	'9F42	51	D1	799	CMPL	R1,#CTL\$AL_STACK[R2]	:TOP ADDRESS OF STACK IN RANGE?
	0F	1A	015E	800	BGTRU	50\$:IF GTRU NO
	52	03	D1	801	CMPL	#PSL\$C_USER,R2	:PREVIOUS MODE USER?
	30	13	0163	802	BEQL	70\$:IF EQL YES
00000000	'9F42	50	D1	803	CMPL	R0,#CTL\$AL_STACKLIM[R2]	:BOTTOM ADDRESS OF STACK IN RANGE?
	26	1E	016D	804	BGEQU	70\$:IF GEQU YES
51	6E	0292	9E	805	MOVAB	W*BADSTACK,(SP)	:SET BAD STACK RETURN
	00000000	'9F42	D0	806	MOVL	#CTL\$AL_STACK[R2],R1	:GET STARTING ADDRESS OF PREVIOUS MODE STACK
		01A9	30	807	BSBW	CHECK_STACK	:CHECK STACK RANGE
		14	12	808	BNEQ	70\$:IF NEQ SUCCESSFUL RANGE CHECK
		71	DF	809	PUSHAL	-(R1)	:PUSH TOP ADDRESS OF STACK RANGE
	7E	FC04	C1	810	MOVAB	-1024+4(R1),-(SP)	:PUSH BOTTOM ADDRESS OF STACK RANGE
		18	10	811	BSBB	CRESTACK	:RE-CREATE STACK SPACE
	5E	08	C0	812	ADDL	#8,SP	:REMOVE VIRTUAL ADDRESS LIMITS FROM STACK
51	00000000	'9F42	D0	813	MOVL	#CTL\$AL_STACK[R2],R1	:GET STARTING ADDRESS OF PREVIOUS MODE STACK
	50	53	78	814	ASHL	#2,R3,R0	:CALCULATE NUMBER OF BYTES TO MOVE
		51	C2	815	SUBL	R0,R1	:CALCULATE NEW TOP OF STACK ADDRESS
		52	DA	816	MTPR	R1,R2	:SET NEW PREVIOUS MODE STACK POINTER
		016C	31	817	BRW	COPYARGS	
			01A2	818			
			01A2	819	.DSABL	LSB	
			01A2	820			
			01A2	821			


```
01A2 822 : SUBROUTINE TO CREATE VIRTUAL SPACE WHERE THE STACK SHOULD BE. TOP
01A2 823 : OF STACK (UNDER THE CALL PC) IS A VA DESCRIPTOR; R2 CONTAINS ACCESS
01A2 824 : MODE.
01A2 825 :
01A2 826 :
01A2 827 CRESTACK:
01A2 828 $SETSFM_S #0 ;TURN OFF SYSTEM SERVICE EXCEPTIONS
51 04 AE 9E 01AB 829 MOVAB -4(SP),R1 ;SET ADDRESS OF VIRTUAL ADDRESS LIMITS
50 DD 01AF 830 PUSHL R0 ;SAVE PREVIOUS STATE OF FAILURE MODE
09 8E D1 01B1 831 $CRETVA_S (R1),(R1),R2 ;CREATE STACK PAGES FOR EXCEPTION
OE 12 01BE 832 CMPL -(SP)+,#SS$_WASSET ;WAS SYS. SERV. FAILURE EXCEP. SET?
50 DD 01C1 833 BNEQ 10$ ;NO
01 50 8ED0 01C3 834 PUSHL R0 ;YES, SAVE STATUS FROM $CRETVA
01 50 E9 01C5 835 $SETSFM_S #1 ;AND SET IT AGAIN
05 01CE 836 POPL -R0 ;RESTORE STATUS FROM $CRETVA
01D1 837 10$: BLBC R0,VAFAIL ;DEAL WITH FAILURE TO CREATE STACK
01D4 838 RSB
01D5 839 :
01D5 840 : TO HERE ON FAILURE TO CREATE VIRTUAL ADDRESS SPACE FOR THE BASE STACK.
01D5 841 : THIS ONLY OCCURS (1) IF THE USER HAS DELETED HIS ORIGINAL STACK AND
01D5 842 : THEN RUN OUT HIS VIRTUAL ADDRESS SPACE, OR (2) IF THE STACK BASE AND
01D5 843 : LIMIT REGISTERS ARE SCROZZLED. ACTION DEPENDS ON THE ACCESS MODE OF
01D5 844 : THE ORIGINAL EXCEPTION: FOR USER AND SUPER MODE, WE QUIETLY DELETE
01D5 845 : THE PROCESS; FOR EXEC AND KERNEL MODE WE BUGCHECK NON-FATALLY AND
01D5 846 : FATALLY, RESPECTIVELY.
01D5 847 :
01D5 848 : NOTE: R2 CONTAINS PREVIOUS ACCESS MODE
01D5 849 :
01 52 D1 01D5 850 VAFAIL: CMPL R2,#PSL$_EXEC ;CHECK ACCESS MODE OF EXCEPTION
11 1F 01D8 851 BLSSU 20$ ;BRANCH IF KERNEL
04 1A 01DA 852 BGTRU 10$ ;BRANCH IF USER OR SUPER
01DC 853 BUG_CHECK UNABLCREVA ;NON-FATAL FOR EXEC MODE
01E0 854 10$: $DE[PRC_S ;BYE, BYE
01EB 855 20$: BUG_CHECK UNABLCREVA,FATAL ;FATAL FOR KERNEL MODE
```



```
01EF 857 .SBTTL SEARCH FOR AND CALL CONDITION HANDLER
01EF 858 :
01EF 859 : PUSH ARGUMENT LIST ON STACK
01EF 860 :
01EF 861 :
01EF 862 .ENABL LSB
01EF 863 NORMAL: ;NORMAL EXIT FROM STACK COPY
1C 6E DF 01EF 864 PUSHAL (SP) ;PUSH ADDRESS OF MECHANISM ARGUMENTS
AE DF 01F1 865 PUSHAL 28(SP) ;PUSH ADDRESS OF SIGNAL ARGUMENTS
02 DD 01F4 866 PUSHL #2 ;PUSH NUMBER OF ARGUMENTS
01F6 867
01F6 868 ; CHECK IF THIS EXCEPTION SHOULD BE MODIFIED BY AN INSTRUCTION EMULATOR
01F6 869
51 00000000'EF D0 01F6 870 MOVL L^EXES$GL_VAXEXCVEC,R1 ;MODIFICATION ROUTINE SUPPLIED?
02 13 01FD 871 BEQL EXES$SRCHANDLER ;BRANCH IF NONE
61 16 01FF 872 JSB (R1) ;OTHERWISE, GO THERE
0201 873 :
0201 874 : CHECK THE PC OF THE EXCEPTION. IF IT IS IN THE CONDITION HANDLER CALL
0201 875 : VECTOR, THEN AN EXCEPTION HAS OCCURRED ATTEMPTING TO CALL A CONDITION
0201 876 : HANDLER (E.G., DUE TO BAD ADDRESS OR ENTRY MASK). IF THIS IS THE CASE,
0201 877 : EXIT THE IMAGE TO AVOID AN EXCEPTION LOOP. WE DO THE SAME FOR CALLS
0201 878 : TO AST ROUTINES. WHILE THIS IS NOT STRICTLY A BAD STACK, REPORTING THE
0201 879 : EXCEPTION WITH THE AST CONTEXT RECORDED IN THE STACK IS SUCH A PAIN
0201 880 : THAT IT IS NOT WORTH IT. THE SPECIAL CASE OF A T-BIT PENDING EXCEPTION
0201 881 : IS ALLOWED SINCE THIS CASE CANNOT RESULT IN A LOOP.
0201 882 :
0201 883 EXES$SRCHANDLER:: ;ENTRY POINT FOR EXTERNAL USE
0201 884 MOVBL 36(SP),35(SP) ;SAVE SIGNAL VECTOR LENGTH
00000464 8F 24 AE 90 0206 885 CML 40(SP),#SS$_TBIT ;CHECK FOR T-BIT PENDING EXCEPTION
28 AE 19 13 020E 886 BEQL 10$ ;BRANCH IF YES - SKIP CHECKS
51 24 AE 08 C1 0210 887 ADDL3 #8,36(SP),R1 ;COMPUTE LONGWORD OFFSET TO SAVED PC
00000000'8F 6E41 D1 0215 888 CML (SP)[R1],#SYSS$CALL_HANDL ;COMPARE TO HANDLER CALL SITE
4E 13 021D 889 BEQL BAD_HANDLER ;BRANCH IF YES
00000000'8F 6E41 D1 021F 890 CML (SP)[R1],#EXES$ASTDEL ;COMPARE TO AST CALL SITE
5E 13 0227 891 BEQL BAD_AST ;BRANCH IF YES
0229 892
0229 893 :
0229 894 : SEARCH FOR CONDITION HANDLER
0229 895 :
0345'CF 6E FA 0229 896 10$: CALLG (SP),W^SEARCH ;SEARCH FOR CONDITION HANDLER
6D 50 E9 022E 897 BLBC R0,20$ ;IF LBC FATAL ERROR
0231 898
28 AE 06 20 AE 01 E1 0231 899 BBC #1,32(SP),11$ ;BRANCH IF THIS IS NOT A STOP
03 00 04 F0 0236 900 INSV #ST$K_SEVERE,#ST$V_SEVERITY,#ST$S_SEVERITY,40(SP) ;FOR STOP, FORCE SEVERITY TO FATAL
023C 901
023C 902 :
023C 903 : CALL CONDITION HANDLER
023C 904 :
023C 905 :
00000000'9F 16 023C 906 11$: JSB @#SYSS$CALL_HANDL ;CALL HANDLER VIA SYSTEM VECTOR
E4 50 E9 0242 907 BLBC R0,10$ ;IF LBC RESIGNAL
12 20 AE 01 E0 0245 908 BBS #1,32(SP),CONT_FROM_STOP ;BRANCH IF ATTEMPTING TO CONTINUE FROM STOP
024A 909 :
024A 910 : CONTINUE FROM EXCEPTION. REMOVE THE SIGNAL ARGUMENT LISTS FROM THE
024A 911 : STACK AND RESUME PROCESSING.
024A 912 :
024A 913 EXES$CONTSIGNAL::
```



```
6E 23 AE 9A 024A 914 MOVZBL 35(SP), (SP) ;GET ORIGINAL SIGNAL ARG COUNT
6E 08 C0 024E 915 ADDL #8, (SP) ;CALCULATE LONGWORD OFFSET TO SAVED PC
6E 04 C4 0251 916 MULL #4, (SP) ;CALCULATE NUMBER OF BYTES TO REMOVE
50 18 AE 7D 0254 917 MOVQ 24(SP), R0 ;RESTORE R0 AND R1
5E 6E C0 0258 918 ADDL (SP), SP ;REMOVE ARGUMENT LIST FROM STACK
02 025B 919 REI ;
025C 920 ;
025C 921 ;
025C 922 ; TO HERE ON ATTEMPT TO CONTINUE FORM A CALL TO STOP
025C 923 ;
025C 924 CONT_FROM_STOP: ;SET FINAL STATUS AND MESSAGE
50 00000001'8F D0 025C 925 MOVL #<LIB$_ATTCONSTO&^CSTSSM_SEVERITY>!ATTCONSTO_IDX, R0
FFFFFFFFD 8F 14 AE D1 0263 926 CMPL 20(SP), #-3 ;SEE IF JUST CALLED LAST CHANCE HANDLER
12 11 026B 927 BRB 12$ ;AND FLOW INTO EXIT CODE
026D 928 ;
026D 929 ;
026D 930 ; TO HERE IF AN EXCEPTION OCCURRED ATTEMPTING TO CALL A HANDLER
026D 931 ;
026D 932 BAD_HANDLER:
50 28 AE D0 026D 933 MOVL 40(SP), R0 ;SET CONDITION AS FINAL STATUS
0271 934 ;SET MESSAGE STRING
50 03 00 02 F0 0271 935 INSV #BADHANDLER_IDX, #STSSV_SEVERITY, #STSS$SEVERITY, R0
FFFFFFFFD 8F 20 AE 41 D1 0276 936 CMPL 32(SP)[R1], #-3 ;SEE IF TRYING TO CALL LAST CHANCE HANDLER
1D 12 027F 937 12$: BNEQ 20$ ;IF NOT, GO TO CALL IT
20 AE 50 D0 0281 938 MOVL R0, 32(SP) ;SAVE CONDITION AND MESSAGE
41 11 0285 939 BRB 30$ ;IF YES, DON'T CALL IT AGAIN
0287 940 ;
0287 941 ;
0287 942 ; TO HERE IF AN EXCEPTION OCCURRED ATTEMPTING TO CALL AN AST
0287 943 ;
0287 944 BAD_AST:
50 28 AE D0 0287 945 MOVL 40(SP), R0 ;SET CONDITION AS FINAL STATUS
028B 946 ;SET MESSAGE STRING
50 03 00 03 F0 028B 947 INSV #BADAST_IDX, #STSSV_SEVERITY, #STSS$SEVERITY, R0
OC 11 0290 948 BRB 20$
0292 949 ;
0292 950 ; BAD STACK WHEN TRYING TO COPY EXCEPTION ARGUMENTS
0292 951 ;
0292 952 ;
0292 953 BADSTACK:
6E DF 0292 954 PUSHAL (SP) ;BAD STACK EXIT FROM STACK COPY
1C AE DF 0294 955 PUSHAL 28(SP) ;PUSH ADDRESS OF MECHANISM ARGUMENTS
02 DD 0297 956 PUSHL #2 ;PUSH ADDRESS OF SIGNAL ARGUMENTS
0299 957 ;PUSH NUMBER OF ARGUMENTS
50 02B0 8F 3C 0299 958 MOVZWL #<SS$BADSTACK&^CSTSSM_SEVERITY>!FINAL_IDX, R0 ;SET BAD STACK STATUS
029E 959 ;
20 AE 50 D0 029E 960 20$: MOVL R0, 32(SP) ;SAVE FINAL STATUS AND MESSAGE
02A2 961 $SETSFMS #0 ;CLEAR SYS. SERVICE FAILURE EXCEP. MODE
50 50 02 50 DC 02AB 962 MOVPSL R0 ;READ CURRENT PSL
51 00000000'9F 40 D0 02AD 963 EXTZV #PSL$V_CURMOD, #PSL$CURMOD, R0, R0 ;EXTRACT CURRENT MODE
OC 13 02BA 964 MOVL @#CTL$AL_FINALEXC[R0], R1 ;GET ADDRESS OF LAST CHANCE HANDLER
14 AE 03 CE 02BC 965 BEQL 30$ ;IF EQL NONE
00000000'9F 16 02C0 966 MNEGL #3, 20(SP) ;SET FRAME DEPTH TO MINUS THREE
OC 11 02C6 967 JSB @#SYS$CALL_HANDL ;CALL LAST CHANCE CONDITION HANDLER
50 DC 02C8 968 BRB 35$
02C8 969 ;
02C8 970 30$: MOVPSL R0 ;READ CURRENT PSL
```



```
50 50 02 18 EF 02CA 971 EXTZV #PSL$V_CURMOD,#PSL$S_CURMOD,R0,R0 ;EXTRACT CURRENT MODE
50 50 01 D1 02CF 972 CMPL #PSL$C_EXEC,R0 ;EXECUTIVE OR KERNEL MODE?
50 20 AE 03 2E 1E 02D2 973 BGEQU 45$ ;IF GEQU YES
00000000'9F 95 02D4 974 35$: EXTZV #ST$SV_SEVERITY,#ST$SS_SEVERITY,32(SP),R0 ;GET MESSAGE INDEX
0E 12 02DA 975 TSTB @#CTL$GB_SSFILTER ;ARE SYSTEM SERVICES INHIBITED?
6E 9F 02E0 976 BNEQ 40$ ;YES, DON'T TRY TO PRINT ANYTHING
FD17 CF40 DD 02E4 977 PUSHAB (SP) ;PUSH ADDRESS OF CONDITION ARGUMENT LIST
00000000'EF 02 FB 02E9 978 PUSHL MSG_VECTOR[R0] ;PUSH ADDRESS OF FINAL EXCEPTION MESSAGE
50 50 20 AE D0 02F0 979 CALLS #2,EXE$EXCMMSG ;PRINT FINAL EXCEPTION MESSAGE
50 03 00 04 F0 02F4 980 40$: MOVL 32(SP),R0 ;RETRIEVE FINAL STATUS
02F9 981 INSV #ST$SK_SEVERE,#ST$SV_SEVERITY,#ST$SS_SEVERITY,R0
0302 982 $EXIT_S R0 ;EXIT PROCESS
06 1A 0302 983 45$: BGTRU 50$ ;BRANCH IF KERNEL MODE
0304 984 BUG_CHECK FATALEXCPT ;FATAL EXECUTIVE MODE EXCEPTION
E6 11 0308 985 BRB 40$ ;GO DELETE THE PROCESS
030A 986
030A 987 50$: BUG_CHECK FATALEXCPT,FATAL ;FATAL KERNEL MODE EXCEPTION
030E 988
030E 989 .DSABL LSB
030E 990
030E 991
030E 992 :
030E 993 : COPY ARGUMENTS TO PREVIOUS MODE STACK AND EXIT TO PREVIOUS MODE
030E 994 :
030E 995 :
030E 996 COPYARGS: ;COPY ARGUMENT LISTS TO PREVIOUS MODE STACK
50 10 AE 9E 030E 997 MOVAB 16(SP),R0 ;GET ADDRESS OF ARGUMENTS TO COPY
81 80 D0 0312 998 10$: MOVL (R0)+(R1)+ ;COPY EXCEPTION ARGUMENTS TO PREVIOUS STACK
FA 53 F5 0315 999 SOBGR R3,10$ ;ANY MORE LONGWORDS TO COPY?
70 C8000010 8F CA 0318 1000 BICL #PSL$M_CM!PSL$M_TBIT!- ;CLEAR COMPATIBILITY, T-BIT, T PENDING, AND
031F 1001 PSL$M_FPD!PSL$M_TP,-(R0) ;FIRST PART DONE
70 8ED0 031F 1002 POPL -(R0) ;SET RETURN ADDRESS
1C BA 0322 1003 POPR #*M<R2,R3,R4> ;RESTORE REGISTERS R2, R3, R4
5E 50 D0 0324 1004 MOVL R0,SP ;REMOVE ARGUMENTS FROM KERNAL STACK
02 0327 1005 REI
0328 1006
0328 1007 :
0328 1008 : SUBROUTINE TO CHECK ACCESSIBILITY OF STACK ADDRESS RANGE
0328 1009 :
0328 1010 : INPUTS:
0328 1011 : R1 - STACK POINTER
0328 1012 : R3 - PARTIAL LONGWORD COUNT
0328 1013 :
0328 1014 : OUTPUTS:
0328 1015 : R0 - BOTTOM ADDRESS OF RANGE
0328 1016 : Z CONDITION CODE - 0 IF ACCESSIBLE, ELSE 1
0328 1017 :
0328 1018 : R1,R2,R3 ARE PRESERVED.
0328 1019 :
0328 1020 CHECK_STACK: ;CHECK STACK ADDRESS RANGE
51 53 0E BB 0328 1021 PUSHR #*M<R1,R2,R3> ;SAVE REGISTERS
51 15 C1 032A 1022 ADDL3 #3+1+17,R3,R1 ;CALCULATE TOTAL LONGWORDS IN RANGE
50 51 04 C4 032E 1023 MULL #4,R1 ;CALCULATE NUMBER OF BYTES IN RANGE
50 6E 51 C3 0331 1024 SUBL3 R1,(SP),R0 ;CALCULATE BOTTOM ADDRESS OF RANGE
00000000'EF 53 DD 0335 1025 PUSHL R0 ;SAVE THIS QUANTITY
D4 0337 1026 CLRL R3 ;ACCESS MODE TO MAXIMIZE WITH PSL<PRVMOD>
16 0339 1027 JSB EXE$PROBEW ;CHECK WRITE ACCESS
```


EXCEPTION
V04-000

B 9
- EXCEPTION HANDLING
SEARCH FOR AND CALL CONDITION HANDLER

16-SEP-1984 00:06:28 VAX/VMS Macro V04-00
5-SEP-1984 03:41:43 [SYS.SRC]EXCEPTION.MAR;1

Page 29
(20)

50	01	D3	033F	1028	BITL	#1,R0	;SET CONDITION CODE
	OF	BA	0342	1029	POPR	#^M<R0,R1,R2,R3>	;RESTORE REGISTERS (NOTE: COND. CODES
			0344	1030			; PRESERVED
		05	0344	1031	RSB		;RETURN


```
0345 1033 .SBTTL SEARCH FOR CONDITION HANDLER
0345 1034 :
0345 1035 : SEARCH - SEARCH FOR CONDITION HANDLER
0345 1036 :
0345 1037 : THIS IS A SPECIAL INTERNAL ROUTINE THAT IS CALLED IN THE INITIAL SEARCH
0345 1038 : FOR A CONDITION HANDLER AND ON RESIGNAL FROM A PREVIOUSLY SIGNALLED
0345 1039 : CONDITION.
0345 1040 :
0345 1041 : INPUTS:
0345 1042 :
0345 1043 : 00(AP) = NUMBER OF CONDITION ARGUMENTS.
0345 1044 : 04(AP) = ADDRESS OF SIGNAL ARGUMENT LIST.
0345 1045 : 08(AP) = ADDRESS OF MECHANISM ARGUMENT LIST.
0345 1046 : 12(AP) = NUMBER OF MECHANISM ARGUMENTS.
0345 1047 : 16(AP) = FP OF HANDLER ESTABLISHER FRAME.
0345 1048 : 20(AP) = FRAME DEPTH.
0345 1049 : 24(AP) = SAVED R0.
0345 1050 : 28(AP) = SAVED R1.
0345 1051 : 32(AP) = FLAGS LONGWORD
0345 1052 : 36(AP) = NUMBER OF SIGNAL ARGUMENTS.
0345 1053 : 40(AP) = EXCEPTION NAME (INTEGER VALUE).
0345 1054 : 44(AP) = FIRST EXCEPTION PARAMETER (IF ANY).
0345 1055 : 48(AP) = SECOND EXCEPTION PARAMETER (IF ANY).
0345 1056 :
0345 1057 :
0345 1058 :
0345 1059 : 40+N*4(AP) = N'TH EXCEPTION PARAMETER (IF ANY).
0345 1060 : 40+N*4+4(AP) = EXCEPTION PC.
0345 1061 : 40+N*4+8(AP) = EXCEPTION PSL.
0345 1062 :
0345 1063 : OUTPUTS:
0345 1064 :
0345 1065 : R0 LOW BIT CLEAR INDICATES FAILURE TO LOCATE CONDITION HANDLER.
0345 1066 :
0345 1067 : R0 = SSS_ACCVIO - STACK CANNOT BE READ FROM CURRENT MODE.
0345 1068 :
0345 1069 : R0 = SSS_NOHANDLER - NO CONDITION HANDLER COULD BE FOUND.
0345 1070 :
0345 1071 : R0 LOW BIT SET INDICATES SUCCESSFUL COMPLETION.
0345 1072 :
0345 1073 : R1 = ADDRESS OF CONDITION HANDLER.
0345 1074 :
0345 1075 :
0345 1076 : .ENABLE LSB
0345 1077 :
0345 1078 : SEARCH:
0345 1079 :
0345 1080 : .WORD 0 ;SEARCH FOR CONDITION HANDLER
0345 1081 : MOVAB W*EXESSIGTORET,(FP) ;ENTRY MASK
0345 1082 : MOVL 16(AP),R0 ;SET ADDRESS OF CONDITION HANDLER
0345 1083 : MOVPSL R1 ;GET PREVIOUS FRAME ADDRESS
0345 1084 : EXTZV #PSL$V_CURMOD,#PSL$S_CURMOD,R1,R1 ;READ CURRENT PSL
0345 1085 : INCL 20(AP) ;EXTRACT CURRENT MODE
0345 1086 : BEQL 50$ ;INCREMENT FRAME DEPTH
0345 1087 : BGTR 40$ ;IF EQL FIRST STACK FRAME
0345 1088 : MOVAQ @#CTL$AQ_EXCVEC[R1],R0 ;IF GTR OTHER STACK FRAME
0345 1089 : CMPL #-2,20(AP) ;GET ADDRESS OF EXCEPTION VECTOR QUADWORD
0345 1090 : BEQL 30$ ;EXAMINE PRIMARY VECTOR?
0345 1091 : ;IF EQL YES
```

6D	03F3'CF	0000	9E	0347	1080	
50	10 AC	D0	034C	1081	10\$:	
	51	DC	0350	1082	20\$:	
51	02 18	EF	0352	1083		
	14 AC	D6	0357	1084		
	37	13	035A	1085		
	1B	14	035C	1086		
50	00000000'9F41	7E	035E	1087		
14 AC	FFFFFFFFFE 8F	D1	0366	1088		
	02	13	036E	1089		


```

      80      D5 0370 1090      TSTL      (R0)+      ;ADJUST TO SECONDARY VECTOR
      51      60      D0 0372 1091 30$:      MOVL      (R0),R1      ;GET ADDRESS OF CONDITION HANDLER
      23      12      0375 1092      BNEQ      60$      ;IF NEQ CONDITION HANDLER FOUND
      D3      11      0377 1093      BRB      10$      ;
      70 16      AC      E8 0379 1094 40$:      BLBS      22(AP),100$      ;IF LBS SEARCH COUNT OVERFLOW
      4D      10      037D 1095 45$:      BSBB      CHECK_FP      ;CHECK IF THIS FRAME IS VALID
10 AO 00000004'8F      D1 037F 1096      CMPL      #SYS$CALL_HANDL+4,SAVPC(R0) ;CALL FROM CONDITION DISPATCHER?
      15      13      0387 1097      BEQL      70$      ;BRANCH IF YES - MUST SKIP FRAMES
      50      0C      A0      D0 0389 1098      MOVL      SAVFP(R0),R0      ;GET ADDRESS OF PREVIOUS FRAME
      5E      13      038D 1099      BEQL      100$      ;IF EQL NONE
      10 AC      50      D0 038F 1100 48$:      MOVL      R0,16(AP)      ;SAVE ADDRESS OF ESTABLISHER FRAME
      37      10      0393 1101 50$:      BSBB      CHECK_FP      ;CHECK IF THIS FRAME IS VALID
      51      60      D0 0395 1102      MOVL      (R0),R1      ;GET ADDRESS OF CONDITION HANDLER
      B2      13      0398 1103      BEQL      10$      ;IF EQL NONE
      50      01      C8 039A 1104 60$:      BISL      #1,R0      ;INDICATE SUCCESSFUL COMPLETION
      04      039D 1105      RET      ;
      039E 1106
51      06 AO      0C      00      EF 039E 1107 70$:      EXTZV      #0,#12,SAVMSK(R0),R1 ;GET REGISTER SAVE MASK
7E      06 AO      02      0E      EF 03A4 1108      EXTZV      #14,#2,SAVMSK(R0),-(SP) ;GET STACK ALIGNMENT BIAS
      50      14      C0 03AA 1109      ADDL      #SAVRG,R0      ;ADD OFFSET TO REGISTER SAVE AREA
      50      8E      C0 03AD 1110      ADDL      (SP)+,R0      ;ADD STACK ALIGNMENT BIAS
      03 51      E9 03B0 1111 80$:      BLBC      R1,90$      ;IF LBC CORRESPONDING REGISTER NOT SAVED
      50      04      C0 03B3 1112      ADDL      #4,R0      ;ADJUST FOR SAVED REGISTER
      51      51      FF 8F 78 03B6 1113 90$:      ASHL      #-1,R1,R1      ;ANY MORE REGISTERS SAVED?
      F3      12      03BB 1114      BNEQ      80$      ;IF NEQ YES
      51      0C      A0      D0 03BD 1115      MOVL      CHF$M_MCHARGLST+4(R0),R1 ;GET ADDRESS OF MECHANISM ARGUMENTS
      50      04      A1      D0 03C1 1116      MOVL      CHF$M_MCH_FRAME(R1),R0 ;GET ADDRESS OF ESTABLISHER FRAME
      08      A1      D5 03C5 1117      TSTL      CHF$M_MCH_DEPTH(R1) ;CHECK IF THIS IS A VECTORED HANDLER
      C5      19      03C8 1118      BLSS      48$      ;IF SO, DON'T SKIP 'ESTABLISHER'
      B1      11      03CA 1119      BRB      45$      ;
      03CC 1120
      03CC 1121 ;
      03CC 1122 ; SUBROUTINE TO VALIDATE THE CURRENT FRAME ADDRESS. THIS IS DONE WITH
      03CC 1123 ; A RANGE CHECK AGAINST THE STACK LIMIT REGISTERS IN THE P1 VECTOR PAGE.
      03CC 1124 ; SINCE FP LINKAGES EXTEND ACROSS ACCESS MODES, THERE IS NO OTHER CHECK
      03CC 1125 ; POSSIBLE TO PREVENT CHASING AN INNER MODE EXCEPTION OUT TO AN OUTER
      03CC 1126 ; ACCESS MODE.
      03CC 1127 ;
      03CC 1128 CHECK_FP:
      51      51      02      51      DC 03CC 1129      MOVPSL      R1      ;READ CURRENT PSL
00000000'9F41      18      EF 03CE 1130      EXTZV      #PSL$V_CURMOD,#PSL$S_CURMOD,R1,R1 ;EXTRACT CURRENT MODE
      50      D1 03D3 1131      CMPL      R0,#CTL$AL_STACK[R1] ;FRAME POINTER WITHIN STACK RANGE?
      10      1A 03DB 1132      BGTRU      100$      ;IF GTRU NO
      51      03      D1 03DD 1133      CMPL      #PSL$C_USER,R1      ;IF IN USER MODE
      0A      13      03E0 1134      BEQL      95$      ;SKIP TOP RANGE CHECK
00000000'9F41      50      D1 03E2 1135      CMPL      R0,#CTL$AL_STACKLIM[R1] ;FRAME POINTER WITHIN STACK RANGE?
      01      1F 03EA 1136      BLSSU      100$      ;IF LSSU NO
      05      05      03EC 1137 95$:      RSB      ;STACK FRAME OK
      50      08F8 8F      3C 03ED 1138 100$:      MOVZWL      #SS$_NOHANDLER,R0 ;SET NO HANDLER FOUND
      04      03F2 1139      RET      ;
      03F3 1140
      03F3 1141      .DISABLE LSB
```



```
03F3 1143 .SBTTL EXE$SIGTORET - TURN EXCEPTION INTO RETURN STATUS
03F3 1144 :++
03F3 1145 : FUNCTIONAL DESCRIPTION:
03F3 1146 :
03F3 1147 : THIS IS A CONDITION HANDLER THAT TURNS AN EXCEPTION IN THE ESTABLISHER
03F3 1148 : FRAME INTO A RETURN FROM THE ESTABLISHER FRAME WITH THE EXCEPTION NAME
03F3 1149 : AS THE STATUS. EXCEPTIONS FROM ANY FRAME OTHER THAN THE ESTABLISHER
03F3 1150 : ARE RESIGNALLED. UNWINDS ARE IGNORED.
03F3 1151 :
03F3 1152 : INPUT PARAMETERS:
03F3 1153 : 00(AP) = NUMBER OF CONDITION ARGUMENTS.
03F3 1154 : 04(AP) = ADDRESS OF SIGNAL ARGUMENT LIST.
03F3 1155 : 08(AP) = ADDRESS OF MECHANISM ARGUMENT LIST.
03F3 1156 :
03F3 1157 : OUTPUT PARAMETERS:
03F3 1158 : R0 - COMPLETION STATUS CODE
03F3 1159 : SS$_RESIGNAL - ALWAYS
03F3 1160 :
03F3 1161 :
0000 03F3 1162 EXE$SIGTORET::
03F3 1163 .WORD 0
03F5 1164
03F5 1165 ASSUME CHF$_MCHARGLIST,EQ,CHF$_SIGARGLIST+4
03F5 1166 MOVQ CHF$_SIGARGLIST(AP),R0 ; GET ADDRESS OF SIGNAL ARGUMENT LIST
04 A0 00000920 8F D1 03F9 1167 CMPL #SS$_UNWIND,CHF$_SIG_NAME(R0) ; UNWINDING?
03F5 1168 BEQL 10$ ; BRANCH TO EXIT IF YES
03F5 1169 TSTL CHF$_MCH_DEPTH(R1) ; EXCEPTION WITHIN ESTABLISHER FRAME?
03F5 1170 BNEQ 10$ ; BRANCH AND RETURN RESIGNAL IF NO
0C A1 04 A0 D0 0408 1171 MOVL CHF$_SIG_NAME(R0),CHF$_MCH_SAVRO(R1) ; SET RETURN STATUS
03F5 1172 CLRQ -(SP) ; CLEAR DEPTH AND NEW PC ARGUMENTS
0000'CF 02 FB 040F 1173 CALLS #2,W^EXE$UNWIND ; UNWIND TO ESTABLISHER'S CALLER
50 0918 8F 3C 0414 1174 10$: MOVZWL #SS$_RESIGNAL,R0 ; RETURN RESIGNAL STATUS
04 0419 1175 RET ;
```



```
041A 1177 .SBTTL EXE$EXPANDSTK - EXPAND USER STACK
041A 1178 :++
041A 1179 : FUNCTIONAL DESCRIPTION:
041A 1180 : EXPAND STACK IS CALLED BY EXE$ACVIOLAT, REFLECT, AND SYSS$ADJSTK
041A 1181 : TO ALLOCATE MORE SPACE TO THE USER STACK.
041A 1182 :
041A 1183 : INPUT PARAMTERS:
041A 1184 : R2 - VIRTUAL ADDRESS LOWER BOUND FOR STACK.
041A 1185 :
041A 1186 : OUTPUT PARAMETERS:
041A 1187 : R0 - COMPLETION STATUS CODE
041A 1188 : SSS_NORMAL - SUCCESSFUL COMPLETION
041A 1189 : SSS_VASFULL - VIRTUAL ADDRESS SPACE FULL
041A 1190 : SSS_PAGOWNVIO - PAGE OWNER VIOLATION
041A 1191 : SSS_EXQUOTA - PAGING FILE QUOTA EXCEEDED
041A 1192 : SSS_INSFWSL - INSUFFICIENT WORKING SET SIZE
041A 1193 :--
041A 1194 EXE$EXPANDSTK::
54 00000000'9F BB 041A 1195 PUSH R1,R2,R3,R4,R5 ; SAVE WORKING REGISTERS
0000000C'9F 52 D0 041C 1196 MOV R0,PCB ; GET PCB ADDRESS
5A 52 1E E1 0423 1197 CMPL R2,@CTL$AL_STACK+12 ; IS ADDRESS IN USER STACK?
55 00000000'9F D0 042A 1198 BGTRU 50$ ; NO, DEFINITE ACCESS VIOLATION
00000000'EF 16 D0 042C 1199 BBC #VAS$V P1,R2,50$ ; BR IF NOT P1 SPACE ADDRESS
15 50 E9 0430 1200 MOV R0,PCB ; GET PCB ADDRESS
6C B443 D5 0437 1201 JSB MMG$PTEINDX ; GET LW INDEX TO PTE IN PHD
44 12 D5 043D 1202 BLBC R0,20$ ; BR IF JUST EXPAND REGION
53 D6 0440 1203 TSTL @PCB$PTEINDX[R3] ; CHECK PTE OF ACCVIO VA
6C B443 D5 0444 1204 BNEQ 50$ ; BR IF NOT EMPTY
OB 12 D6 0446 1205 10$: INCL R3 ; NEXT PTE INDEX
52 0200 C2 9E 0448 1206 TSTL @PCB$PTEINDX[R3] ; CHECK PTE FOR EMPTY
F1 11 044C 1207 BNEQ 30$ ; NO, STOPPER FOR CREATE
52 30 A5 D0 044E 1208 MOVAB 512(R2),R2 ; AUGMENT VA BY ANOTHER PAGE
04 AE DD 0453 1209 BRB 10$ ; AND TRY ANOTHER PAGE
53 7E 7E 0455 1210 20$: MOV R0,PCB ; SET ENDING ADDRESS TO FREP1VA
50 0C 3C 0459 1211 30$: PUSHL 4(SP) ; BUILD INADR DESCRIPTOR
3E BA 045C 1212 PUSHL R2 ;
50 05 05 045E 1213 MOVAQ -(SP),R3 ; CREATE SPACE FOR RETADR
13 50 E8 0461 1214 $CRETVA_S 8(R3),R3,#PSL$C_USER ; CREATE SPACE
50 DD 046F 1215 BLBS R0,40$ ; BR IF SUCCESS
50 DD 0472 1216 PUSHL R0 ; SAVE ERROR STATUS
50 8ED0 0474 1217 $DELTVA_S (R3),8(R3),#PSL$C_USER ; DELETE PARTIAL AREA
5E 10 C0 0482 1218 POPL R0 ; RESTORE COMPLETION CODE
03 11 0485 1219 40$: ADDL #16,SP ; CLEAN STACK
50 0C 3C 0488 1220 BRB 60$ ;
50 0C 3C 048A 1221 50$: MOVZWL #SS$ ACCVIO,R0 ; SET ERROR STATUS
3E BA 048D 1222 60$: POP R1,R2,R3,R4,R5 ; RESTORE REGISTERS
05 05 05 048F 1223 RSB ; AND RETURN
0490 1224
0490 1225
```



```
0490 1227 .SBTTL EXESMCHK_PRTCT - MACHINE CHECK RECOVERY BLOCK
0490 1228
0490 1229 :++
0490 1230 : EXESMCHK_PRTCT -ENABLE RECOVERY BLOCK FOR MACHINE CHECK EXCEPTIONS
0490 1231 :
0490 1232 : FUNCTIONAL DESCRIPTION:
0490 1233 :
0490 1234 : ALLOW A SPECIFIED BLOCK OF KERNEL CODE TO PROTECT ITS SELF
0490 1235 : FROM FATAL MACHINE CHECKS, THEN FIND OUT IF ONE OCCURED WITHING
0490 1236 : THE EXECUTION OF THE BLOCK.
0490 1237 :
0490 1238 : INPUTS:
0490 1239 :
0490 1240 : R0 = FUNCTION MASK TO FILTER SPECIFIC TYPES OF MACHINE CHECKS
0490 1241 : (SP) = RETURN ADDRESS (START OF RECOVERY BLOCK)
0490 1242 : 4(SP) = END OF RECOVERY BLOCK ADDRESS
0490 1243 : MUST BE IN KERNEL MODE
0490 1244 : CODE IN RECOVERY BLOCK EXECUTES AT IPL 31
0490 1245 :
0490 1246 : OUTPUTS:
0490 1247 :
0490 1248 : WHEN INSTRUCTION AFTER END OF RECOVERY BLOCK IS REACHED,
0490 1249 : R0 = 0 IF MACHINE CHECK OCCURRED
0490 1250 : R1 = 1 IF MACHINE CHECK DID NOT OCCUR
0490 1251 : ALL OTHER REGISTERS PRESERVED
0490 1252 :
0490 1253 : CALLING SEQUENCE:
0490 1254 :
0490 1255 : PUSHAL END_LABEL ; LABEL, END OF RECOVERY BLOCK ON STACK
0490 1256 : MOVL #MASK,R0 ; FUNCTION FILTER MASK
0490 1257 : JSB EXESMCHK_PRTCT ; INITIATE RECOVERY BLOCK
0490 1258 : ;
0490 1259 : ;
0490 1260 : ;
0490 1261 : RSB ; END OF RECOVERY BLOCK RETURN
0490 1262 : END_LABEL: ; END OF RECOVERY BLOCK LABEL
0490 1263 : BLBS R0,MCHK_OK ; IF LBS, NO MACHINE CHECK OCCURED
0490 1264 : BRW MCHK_ERROR ; ELSE, CODE FAULTED
0490 1265 :--
0490 1266
000001F3 1267 .PSECT $AEXENONPAGED, LONG
01F3 1268
01F3 1269 EXESMCHK_PRTCT::
01F3 1270
7E 0000'CF 7D 01F3 1271 MOVQ W^MCHK$GL_MASK, -(SP) ; SAVE PREVIOUS MASK AND SP - RECURSIVE
01F8 1272 ; SO MACHINE CHECK HANDLER CAN USE PRTCT
01F8 1273 DSBINT ; GO TO IPL 31 FOR REMAINDER OF BLOCK
0000'CF 50 D0 01FE 1274 MOVL R0, W^MCHK$GL_MASK ; CURRENT FUNCTION MASK
0000'CF 5E D0 0203 1275 MOVL SP, W^MCHK$GL_SP ; SAVE CURRENT SP FOR POTENTIAL RECOVERY
OC BE 16 0208 1276 JSB @<3*4>(SP) ; CALL PROTECTED CODE BACK
020B 1277
020B 1278 ; IF PROTECTED CODE EXECUTED WITHOUT A MACHINE CHECK, IT RETURNS HERE
020B 1279
50 01 3C 020B 1280 MOVZWL #SS$_NORMAL, R0 ; NORMAL COMPLETION, NO MACHINE CHECK
020E 1281
020E 1282 ; RESTORE MASK AND SP OF OLD, FINAL RETURN TO CALLER
020E 1283
```


EXCEPTION
V04-000

- EXCEPTION HANDLING
EXESMCHK_PRTCT - MACHINE CHECK RECOVERY

H 9

16-SEP-1984 00:06:28 VAX/VMS Macro V04-00
5-SEP-1984 03:41:43 [SYS.SRC]EXCEPTION.MAR;1

Page 35
(24)

0000'CF	04 AE	7D	020E	1284	PROTECT_RETURN:		
			020E	1285			; COMMON RETURN TO END OF RECOVERY BLOCK
			020E	1286	MOVQ	<1*4>(SP),W^MCHK\$GL_MASK	; RESTORE PREVIOUS MASK AND SP
			0214	1287	ENBINT		; BACK TO ORIGINAL IPL
SE	OC	C0	0217	1288	ADDL	#<3*4>,SP	; CLEAN UP STACK
		05	021A	1289	RSB		; FINAL RETURN TO CALLER AT END OF
			021B	1290			; RECOVERY BLOCK LABEL


```
021B 1292 :++
021B 1293 :
021B 1294 : EXESMCHK_BUGCHK - HANDLE ALL BUGCHECKS FOR WHICH PROTECTION IS DESIRED
021B 1295 :
021B 1296 : FUNCTIONAL DESCRIPTION:
021B 1297 :
021B 1298 :     THIS ROUTINE IS CALLED FROM WITHIN MACHINE CHECK HANDLER JUST
021B 1299 :     BEFORE ISSUING A FATAL BUG-CHECK.  IF A CURRENT PROTECTION BLOCK
021B 1300 :     IS IN EFFECT, A RETURN IS MADE AT THE END OF RECOVERY BLOCK LABEL
021B 1301 :     AFTER PROTECTED CODE.  ELSE, IF NO PROTECTION BLOCK IN EFFECT, RETURN
021B 1302 :     TO MACHINE CHECK WHICH ISSUES THE FATAL BUG-CHECK.
021B 1303 :
021B 1304 : INPUTS:
021B 1305 :
021B 1306 :     (SP) = RETURN ADDRESS TO MACHINE CHECK
021B 1307 :     4(SP) = ADDRESS OF MACHINE CHECK PC,PSL FROM EXCEPTION
021B 1308 :     8(SP) = FUNCTION FILTER MASK BUILT BY MACHINE CHECK, DESCRIBES THE
021B 1309 :             TYPE OF MACHINE CHECK FOR TESTING AGAINST MASK SPECIFIED BY
021B 1310 :             PROTECTED CODE.
021B 1311 :
021B 1312 : OUTPUTS:
021B 1313 :
021B 1314 :     IF NO RECOVERY BLOCK IN EFFECT:
021B 1315 :
021B 1316 :         PC,PSL POINTER AND MASK REMOVED FROM STACK
021B 1317 :         RSB BACK TO MACHINE CHECK
021B 1318 :         ALL REGISTERS PRESERVED
021B 1319 :
021B 1320 :     IF RECOVERY BLOCK IN EFFECT:
021B 1321 :
021B 1322 :         MODE, IPL, STACK SET TO THAT IN EFFECT WHEN RECOVERY BLOCK
021B 1323 :         DECLARED.
021B 1324 :         R0 - CODE INDICATING MACHINE CHECK OCCURED
021B 1325 :         RETURN TO END OF RECOVERY BLOCK LABEL
021B 1326 :         ALL OTHER REGISTERS PRESERVED
021B 1327 :
021B 1328 : --
021B 1329 :
021B 1330 : EXESMCHK_BUGCHK::
021B 1331 :
021B 1332 :     PUSHB    #^M<R0,R1,R2>          ; SAVE SOME REGISTERS
021B 1333 :     MOVQ     <4*4>(SP),R1          ; GET PC,PSL POINTER AND MASK
021B 1334 :     BSBB     MCHK_TEST             ; CURRENTLY A RECOVERY BLOCK?
021B 1335 :     BLBS     R0,15$                ; BRANCH IF YES
021B 1336 :     POPR     #^M<R0,R1,R2>          ; NO RECOVERY BLOCK, RESTORE REGS
021B 1337 :     MOVL     (SP)+,4(SP)            ; MOVE RETURN ADDRESS UP ON STACK
021B 1338 :     ADDL     #<4*1>,SP              ; CLEAR STACK OF MASK
021B 1339 :     RSB      ; RETURN TO MACHINE CHECK HANDLER
021B 1340 :
021B 1341 :     BICB     #MCHK$M_LOG,R2         ; IGNORE LOG INHIBIT BIT
021B 1342 :     BITL     R2,W^MCHK$GL_MASK      ; PROTECTION DESIRED HERE?
021B 1343 :     BEQL     10$                    ; NO, RETURN TO MACHINE CHECK
021B 1344 :     POPR     #^M<R0,R1,R2>          ; RESTORE REGISTERS
021B 1345 :     MOVL     4(SP),SP               ; RESET STACK TO INTERRUPT PC,PSL
021B 1346 :     MOVAL    W^20$, (SP)            ; REI BACK HERE INSTEAD
021B 1347 :     REI      ; BACK TO PROTECTED CODES' MODE, ETC.
021B 1348 :     MOVZWL   #SS$_MCHK,R0          ; ERROR CODE IN R0

51 10 AE 7D 021D 1333    PUSHB    #^M<R0,R1,R2>          ; SAVE SOME REGISTERS
    2F 10 0221 1334    MOVQ     <4*4>(SP),R1          ; GET PC,PSL POINTER AND MASK
    0A 50 E8 0223 1335    BSBB     MCHK_TEST             ; CURRENTLY A RECOVERY BLOCK?
    07 BA 0226 1336    BLBS     R0,15$                ; BRANCH IF YES
04 AE 8E D0 0228 1337    POPR     #^M<R0,R1,R2>          ; NO RECOVERY BLOCK, RESTORE REGS
    5E 04 C0 022C 1338    MOVL     (SP)+,4(SP)            ; MOVE RETURN ADDRESS UP ON STACK
    05 022F 1339    ADDL     #<4*1>,SP              ; CLEAR STACK OF MASK
    0230 1340    RSB      ; RETURN TO MACHINE CHECK HANDLER
0000 52 01 8A 0230 1341    BICB     #MCHK$M_LOG,R2         ; IGNORE LOG INHIBIT BIT
    CF 52 D3 0233 1342    BITL     R2,W^MCHK$GL_MASK      ; PROTECTION DESIRED HERE?
    EC 13 0238 1343    BEQL     10$                    ; NO, RETURN TO MACHINE CHECK
    07 BA 023A 1344    POPR     #^M<R0,R1,R2>          ; RESTORE REGISTERS
    5E 04 AE D0 023C 1345    MOVL     4(SP),SP               ; RESET STACK TO INTERRUPT PC,PSL
6E 0246 CF DE 0240 1346    MOVAL    W^20$, (SP)            ; REI BACK HERE INSTEAD
    02 0245 1347    REI      ; BACK TO PROTECTED CODES' MODE, ETC.
50 02BC 8F 3C 0246 1348    MOVZWL   #SS$_MCHK,R0          ; ERROR CODE IN R0
```


EXCEPTION
V04-000

J 9
- EXCEPTION HANDLING
EXESMCHK_PRTCT - MACHINE CHECK RECOVERY

16-SEP-1984 00:06:28 VAX/VMS Macro V04-00
5-SEP-1984 03:41:43 [SYS.SRC]EXCEPTION.MAR;1

Page 37
(25)

5E	0000'CF	DO	024B	1349	MOVL	W^MCHK\$GL SP,SP	; RESET STACK FOR RETURN
	BC	11	0250	1350	BRB	PROTECT_RETURN	; RETURN TO END OF PROTECTED CODE


```
0252 1352 :++
0252 1353 : MCHK_TEST - TEST TO SEE IF RECOVERY BLCOK ENABLED AT TIME OF MACHINE CHECK
0252 1354 :
0252 1355 : INPUTS:
0252 1356 :
0252 1357 : R1 - POINTER TO PC,PSL OF MACHINE CHECK EXCEPTION
0252 1358 :
0252 1359 : OUTPUTS:
0252 1360 :
0252 1361 : R0 - .TRUE. IF RECOVERY BLOCK CURRENTLY IN EFFECT
0252 1362 : .FALSE. IF NO RECOVERY BLOCK
0252 1363 : ALL OTHER REGISTERS PRESERVED
0252 1364 :
0252 1365 :--
0252 1366 :
0252 1367 MCHK_TEST:
0252 1368
0000 50 D4 0252 1369 CLRL R0 ; ASSUME NO RECOVERY BLOCK
      CF D5 0254 1370 TSTL W^MCHK$GL_SP ; IF SP NOT ZERO, THEN RECOVERY BLCOK
      02 13 0258 1371 BEQL 40$
      50 D6 025A 1372 INCL R0 ; SET LOW BIT, INDICATING RECOVERY BLOCK
      025C 1373 40$:
      05 025C 1374 RSB ; RETURN
```



```
025D 1376 :++
025D 1377 :
025D 1378 : EXESMCHK$_TEST - TEST RECOVERY BLOCK FOR MASK MATCH
025D 1379 :
025D 1380 : FUNCTIONAL DESCRIPTION:
025D 1381 :
025D 1382 :     TEST TO SEE IF MACHINE CHECK RECOVERY BLOCK EXISTS WHEN MACHINE
025D 1383 :     CHECK EXCEPTION OCCURRED.  IF SO, CHECK TO SEE IF FUNCTION MASK
025D 1384 :     BITS MATCH.
025D 1385 :
025D 1386 : INPUTS:
025D 1387 :
025D 1388 :     R1 - POINTS TO PC,PSL PAIR ON STACK FROM MACHINE CHECK
025D 1389 :     R2 - CONTAINS BITS TO TEST AGAINST MASK SPECIFIED BY PROTECTED CODE
025D 1390 :
025D 1391 : OUTPUTS:
025D 1392 :
025D 1393 :     R0 - .TRUE. IF RECOVERY BLOCK IN EFFECT AND MASKS MATCH
025D 1394 :     .FALSE. IF NEITHER RECOVERY BLOCK OR MASK MATCH
025D 1395 :     R2 - DESTROYED
025D 1396 :     ALL OTHER REGISTERS PRESERVED
025D 1397 :
025D 1398 :--
025D 1399 :
025D 1400 EXESMCHK$_TEST::
025D 1401 :
025D 1402 :     BSBB MCHK_TEST ; RECOVERY BLOCK IN EFFECT HERE?
025D 1403 :     BLBC R0,50$ ; NO, RETURN WITH R0 CLEAR
025D 1404 :
025D 1405 :     ASSUME MCHK$_LOG EQ 1
025D 1406 :
025D 1407 :     BLBS R2,60$ ; HANDLE LOG BIT SEPARATELY
025D 1408 :     BITL R2,W^MCHK$GL_MASK ; MASKS MATCH?
025D 1409 :     BNEQ 50$ ; YES
025D 1410 :     CLRL R0 ; NO, R0 = .FALSE.
025D 1411 :     RSB 50$ ; RETURN
025D 1412 :
025D 1413 :     BLBC W^MCHK$GL_MASK,47$ ; ERROR LOG NOT DISABLED
025D 1414 :     DECL R2 ; WANT TO DISABLE LOGGING, CHECK REST
025D 1415 :     BRB 45$ ; OF MASK FOR ERROR TYPE
025D 1416 :
025D 1417 :
025D 1418 : .END
```

OC F3 10 025D 1402 BSBB MCHK_TEST ; RECOVERY BLOCK IN EFFECT HERE?
50 E9 025D 1403 BLBC R0,50\$; NO, RETURN WITH R0 CLEAR

0A 52 E8 025D 1407 BLBS R2,60\$; HANDLE LOG BIT SEPARATELY
0000'CF 52 D3 025D 1408 BITL R2,W^MCHK\$GL_MASK ; MASKS MATCH?
02 12 025D 1409 BNEQ 50\$; YES
50 D4 025D 1410 CLRL R0 ; NO, R0 = .FALSE.
05 025D 1411 RSB 50\$; RETURN

F8 0000'CF E9 025D 1413 BLBC W^MCHK\$GL_MASK,47\$; ERROR LOG NOT DISABLED
52 D7 025D 1414 DECL R2 ; WANT TO DISABLE LOGGING, CHECK REST
ED 11 025D 1415 BRB 45\$; OF MASK FOR ERROR TYPE

EXCEPTION
Symbol table

- EXCEPTION HANDLING

M 9

16-SEP-1984 00:06:28 VAX/VMS Macro V04-00
5-SEP-1984 03:41:43 [SYS.SRC]EXCEPTION.MAR;1

Page 40
(27)

ACVIOLAT	00000063	R	03
ATTCONSTO_IDX	= 00000001		
ATTCONSTO_MSG	00000033	R	02
BADAST_IDX	= 00000003		
BADAST_MSG	00000083	R	02
BADHANDLER_IDX	= 00000002		
BADHANDLER_MSG	00000052	R	02
BADSTACK	00000292	R	02
BAD_AST	00000287	R	02
BAD_HANDLER	0000026D	R	02
BUGS_FATALEXCPT	*****	X	02
BUGS_INVEXCEPTN	*****	X	03
BUGS_KRNLSTAKNV	*****	X	03
BUGS_UNABLCREVA	*****	X	02
CHECK_FP	000003CC	R	02
CHECK_STACK	00000328	R	02
CHFSL_MCHARGLST	= 00000008		
CHFSL_MCH_DEPTH	= 00000008		
CHFSL_MCH_FRAME	= 00000004		
CHFSL_MCH_SAVRO	= 0000000C		
CHFSL_SIGARGLST	= 00000004		
CHFSL_SIG_NAME	= 00000004		
CONT_FROM_STOP	0000025C	R	02
COPYARGS	0000030E	R	02
CRESTACK	000001A2	R	02
CTLSAL_CMCNTX	*****	X	03
CTLSAL_FINALEXC	*****	X	02
CTLSAL_STACK	*****	X	02
CTLSAL_STACKLIM	*****	X	02
CTLSAQ_EXCVEC	*****	X	02
CTL\$GB_SSFILTER	*****	X	02
CTL\$GL_CMHANDLR	*****	X	03
CTL\$GL_CMSUPR	*****	X	03
CTL\$GL_CMUSER	*****	X	03
CTL\$GL_PCB	*****	X	02
CTL\$GL_PHD	*****	X	02
EX3ARG	0000017B	R	03
EX4ARG	00000106	R	03
EX5ARG	00000157	R	03
EXCCMD	000000BF	R	03
EX\$ACVIOLAT	00000000	RG	03
EX\$ARITH	0000006C	RG	03
EX\$ASTDEL	*****	X	02
EX\$ASTFLT	00000077	RG	03
EX\$BREAK	0000008C	RG	03
EX\$BUG_CHECK	*****	X	03
EX\$CMODSUPR	00000094	RG	03
EX\$CMODUSER	000000AC	RG	03
EX\$COMPAT	000000CC	RG	03
EX\$CONTSIGNAL	0000024A	RG	02
EX\$EXCEPTION	0000018F	RG	03
EX\$EXCMG	*****	X	02
EX\$EXPANDSTK	0000041A	RG	02
EX\$GL_ABSTIM	*****	X	03
EX\$GL_BADACV_C	*****	X	03
EX\$GL_BADACV_T	*****	X	03
EX\$GL_VAXEXCVEC	*****	X	02

EX\$KERSTKNV	0000010C	RG	03
EX\$MCKECHK	00000110	RG	03
EX\$MCHK_BUGCHK	0000021B	RG	03
EX\$MCHK_PRTCT	000001F3	RG	03
EX\$MCHK_TEST	0000025D	RG	03
EX\$OPCCOS	00000118	RG	03
EX\$OPCDEC	00000120	RG	03
EX\$PAGRDERR	00000152	RG	03
EX\$PROBEW	*****	X	02
EX\$RADRMOD	0000015C	RG	03
EX\$REFLECT	000000A6	RG	02
EX\$ROPRAND	00000164	RG	03
EX\$SIGTORET	000003F3	RG	02
EX\$SRCHANDLER	00000201	RG	02
EX\$SSFAIL	00000180	RG	03
EX\$STBIT	0000016C	RG	03
EX\$UNWIND	*****	X	02
EX\$SXT	00000187	R	03
FINALMSG	00000010	R	02
FINAL_IDX	= 00000000		
HANDLER	= 00000000		
IPL\$ASTDEL	= 00000002		
LIB\$ATTCONSTO	*****	X	02
MCHK\$GL_MASK	*****	X	03
MCHK\$GL_SP	*****	X	03
MCHK\$M_COG	= 00000001		
MCHK_TEST	00000252	R	03
MMG\$PTEINDX	*****	X	02
MSG_VECTOR	00000000	R	02
NORMAL	000001EF	R	02
PCB\$PHD	= 0000006C		
PHD\$FREP1VA	= 00000030		
PR\$ IPL	= 00000012		
PROTECT_RETURN	0000020E	R	03
PSL\$C_EXEC	= 00000001		
PSL\$C_SUPER	= 00000002		
PSL\$C_USER	= 00000003		
PSL\$M_CM	= 80000000		
PSL\$M_FPD	= 08000000		
PSL\$M_PRVMOD	= 00C00000		
PSL\$M_TBIT	= 00000010		
PSL\$M_TP	= 40000000		
PSL\$S_CURMOD	= 00000002		
PSL\$S_PRVMOD	= 00000002		
PSL\$V_CM	= 0000001F		
PSL\$V_CURMOD	= 00000018		
PSL\$V_IS	= 0000001A		
PSL\$V_PRVMOD	= 00000016		
REFLECT	0000019A	R	03
SAVAP	= 00000008		
SAVFP	= 0000000C		
SAVMSK	= 00000006		
SAVPC	= 00000010		
SAVPSW	= 00000004		
SAVRG	= 00000014		
SEARCH	00000345	R	02
SS\$ACCVIO	= 0000000C		

EXCEPTION
Symbol table

- EXCEPTION HANDLING

N 9

16-SEP-1984 00:06:28
5-SEP-1984 03:41:43

VAX/VMS Macro V04-00
[SYS.SRC]EXCEPTION.MAR;1

Page 41
(27)

SS\$_ARTRES	=	00000474
SS\$_ASTFLT	=	0000040C
SS\$_BADSTACK	=	000002B4
SS\$_BREAK	=	00000414
SS\$_CMODSUPR	=	0000041C
SS\$_CMODUSER	=	00000424
SS\$_COMPAT	=	0000042C
SS\$_MCHECK	=	000002BC
SS\$_NOHANDLER	=	000008F8
SS\$_NORMAL	=	00000001
SS\$_OPCCUS	=	00000434
SS\$_OPCDEC	=	0000043C
SS\$_PAGRDERR	=	00000444
SS\$_RADRMOD	=	0000044C
SS\$_RESIGNAL	=	00000918
SS\$_ROPRAND	=	00000454
SS\$_SSFAIL	=	0000045C
SS\$_TBIT	=	00000464
SS\$_UNWIND	=	00000920
SS\$_WASSET	=	00000009
ST\$K_SEVERE	=	00000004
ST\$M_SEVERITY	=	00000007
ST\$S_SEVERITY	=	00000003
ST\$V_SEVERITY	=	00000000
SY\$ADJSTK	*****	X 02
SY\$CALL HANDL	*****	X 02
SY\$CRETVA	*****	GX 02
SY\$DELPRC	*****	GX 02
SY\$DELTVA	*****	GX 02
SY\$EXIT	*****	GX 02
SY\$SETSFM	*****	GX 02
V\$V_P1	=	0000001E
V\$FATL	=	000001D5 R 02

+-----+
! Psect synopsis !
+-----+

PSECT name	Allocation	PSECT No.	Attributes														
. ABS .	00000000 (0.)	00 (0.)	NOPIC	USR	CON	ABS	LCL	NOSHR	NOEXE	NORD	NOWRT	NOVEC	BYTE				
\$ABSS	00000000 (0.)	01 (1.)	NOPIC	USR	CON	ABS	LCL	NOSHR	EXE	RD	WRT	NOVEC	BYTE				
YEXEPAGED1	00000490 (1168.)	02 (2.)	NOPIC	USR	CON	REL	LCL	NOSHR	EXE	RD	WRT	NOVEC	LONG				
\$AEXENONPAGED	00000278 (632.)	03 (3.)	NOPIC	USR	CON	REL	LCL	NOSHR	EXE	RD	WRT	NOVEC	LONG				

+-----+
! Performance indicators !
+-----+

Phase	Page faults	CPU Time	Elapsed Time
Initialization	29	00:00:00.10	00:00:00.75
Command processing	107	00:00:00.53	00:00:04.35
Pass 1	336	00:00:11.05	00:00:28.15
Symbol table sort	0	00:00:01.54	00:00:04.80
Pass 2	266	00:00:03.59	00:00:10.22
Symbol table output	18	00:00:00.13	00:00:00.13

EXCEPTION
VAX-11 Macro Run Statistics

- EXCEPTION HANDLING

B 10

16-SEP-1984 00:06:28 VAX/VMS Macro V04-00
5-SEP-1984 03:41:43 [SYS.SRC]EXCEPTION.MAR;1

Page 42
(27)

Psect synopsis output	1	00:00:00.02	00:00:00.02
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	759	00:00:16.97	00:00:48.74

The working set limit was 1800 pages.

66462 bytes (130 pages) of virtual memory were used to buffer the intermediate code.

There were 60 pages of symbol table space allocated to hold 953 non-local and 66 local symbols.

1418 source lines were read in Pass 1, producing 22 object records in Pass 2.

28 pages of virtual memory were used to define 27 macros.

+-----+
! Macro library statistics !
+-----+

Macro library name

Macros defined

\$255\$DUA28:[SYS.OBJ]LIB.MLB;1
\$255\$DUA28:[SYSLIB]STARLET.MLB;2
TOTALS (all libraries)

9
15
24

1026 GETS were required to define 24 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS\$:EXCEPTION/OBJ=OBJ\$:EXCEPTION MSRC\$:EXCEPTION/UPDATE=(ENH\$:EXCEPTION)+EXECML\$/LIB

0374 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY

